

Kernel Application (KERNEL)

version 2.4

Magnus Fröberg

1997-11-17

Typeset in L^AT_EX from SGML source using the DOCBUILDER 3.0 Document System.

Contents

1 KERNEL Reference Manual	1
1.1 kernel (Application)	25
1.2 application (Module)	29
1.3 auth (Module)	36
1.4 code (Module)	39
1.5 disk_log (Module)	47
1.6 erl_boot_server (Module)	59
1.7 erl_ddll (Module)	61
1.8 erl_prim_loader (Module)	64
1.9 erlang (Module)	67
1.10 error_handler (Module)	95
1.11 error_logger (Module)	97
1.12 file (Module)	102
1.13 gen_tcp (Module)	115
1.14 gen_udp (Module)	119
1.15 global (Module)	121
1.16 global_group (Module)	125
1.17 heart (Module)	129
1.18 inet (Module)	131
1.19 init (Module)	138
1.20 net_adm (Module)	142
1.21 net_kernel (Module)	144
1.22 os (Module)	145
1.23 pg2 (Module)	147
1.24 rpc (Module)	149
1.25 seq_trace (Module)	153
1.26 user (Module)	161
1.27 wrap_log_reader (Module)	162
1.28 app (File)	164
1.29 config (File)	166

KERNEL Reference Manual

Short Summaries

- Application **kernel** [page 25] – The Kernel Application
- Erlang Module **application** [page 29] – Functions for controlling applications
- Erlang Module **auth** [page 36] – The Erlang Network Authentication Server
- Erlang Module **code** [page 39] – Erlang Code Server
- Erlang Module **disk_log** [page 47] – A disk based term logging facility
- Erlang Module **erl_boot_server** [page 59] – Boot Server for Other Erlang Machines
- Erlang Module **erl_ddll** [page 61] – Dynamic Driver Loader and Linker
- Erlang Module **erl_prim_loader** [page 64] – The Low Level Erlang Loader.
- Erlang Module **erlang** [page 67] – The Erlang BIFs
- Erlang Module **error_handler** [page 95] – Default System Error Handler
- Erlang Module **error_logger** [page 97] – The Erlang Error Logger
- Erlang Module **file** [page 102] – File Interface Module
- Erlang Module **gen_tcp** [page 115] – Interface to TCP/IP sockets
- Erlang Module **gen_udp** [page 119] – Interface to UDP.
- Erlang Module **global** [page 121] – A Global Name Registration Facility
- Erlang Module **global_group** [page 125] – Grouping Nodes to Global Name Registration Groups
- Erlang Module **heart** [page 129] – Heartbeat Monitoring of an Erlang System.
- Erlang Module **inet** [page 131] – Access to TCP/IP protocols.
- Erlang Module **init** [page 138] – Called at System Start
- Erlang Module **net_adm** [page 142] – Various Erlang Net Administration Routines
- Erlang Module **net_kernel** [page 144] – Erlang Networking Kernel
- Erlang Module **os** [page 145] – Operating System Specific Functions
- Erlang Module **pg2** [page 147] – Distributed Named Process Groups
- Erlang Module **rpc** [page 149] – Remote Procedure Call Services
- Erlang Module **seq_trace** [page 153] – Sequential Tracing of Messages.
- Erlang Module **user** [page 161] – Standard I/O Server
- Erlang Module **wrap_log_reader** [page 162] – A function to read internally formatted wrap disk logs
- File **app** [page 164] – Application resource file
- File **config** [page 166] – Configuration file

kernel

No functions are exported

application

The following functions are exported:

- `get_all_env()`
[page 29] Gets all configuration parameters for the application.
- `get_all_env(Application) -> Env`
[page 29] Gets all configuration parameters for the application.
- `get_all_key()`
[page 29] Gets all the resource file keys for the application.
- `get_all_key(Application) -> {ok, Keys} | undefined`
[page 29] Gets all the resource file keys for the application.
- `get_application()`
[page 30] Gets the name of an application.
- `get_application(Pid | Module) -> {ok, Application} | undefined`
[page 30] Gets the name of an application.
- `get_env(Key)`
[page 30] Gets the value of a configuration parameter.
- `get_env(Application, Key) -> {ok, Value} | undefined`
[page 30] Gets the value of a configuration parameter.
- `get_key(Key)`
[page 30] Gets the value of a configuration parameter.
- `get_key(Application, Key) -> {ok, Value} | undefined`
[page 30] Gets the value of a configuration parameter.
- `load(Application)`
[page 30] Loads an application.
- `load(Application, DistNodes) -> ok | {error, Reason}`
[page 30] Loads an application.
- `loaded_applications() -> [{Name, Description, Version}]`
[page 31] Gets the currently loaded applications
- `permit(Application, Bool) -> ok | {error, Reason}`
[page 31] Changes an application's permission to run on the node
- `start(Application)`
[page 32] Starts an application.
- `start(Application, Type) -> ok | {error, Reason}`
[page 32] Starts an application.
- `start_type() -> normal | local | {takeover, node()} | {failover, node()}`
[page 32] Check the type of start of an application.
- `stop(Application) -> ok`
[page 32] Stops a running application

- `takeover(Application, Type) -> {ok, Pid} | {error, Reason}`
[page 33] Moves a distributed application to the current node
- `which_applications() -> [{Name, Description, Version}]`
[page 33] Gets the currently running applications
- `Module:config_change(Changed, New, Removed) -> ok`
[page 33] Informs an application of changed configuration parameters
- `Module:start(Type, ModuleStartArgs) -> {ok, Pid} | {ok, Pid, State} | {error, Reason}`
[page 34] Starts an application
- `Module:start_phase(Phase, Type, PhaseStartArgs) -> ok | {error, Reason}`
[page 34] Starts an application in the Phase
- `Module:stop(State) -> void()`
[page 35] Called when the application has stopped

auth

The following functions are exported:

- `start()`
[page 37]
- `stop()`
[page 37]
- `open(Name)`
[page 37]
- `is_auth(Node)`
[page 37]
- `exists(Node)`
[page 37]
- `cookie()`
[page 38]
- `node_cookie(Node, Cookie)`
[page 38]
- `node_cookie([Node, Cookie])`
[page 38]
- `cookie([Cookie])`
[page 38]

code

The following functions are exported:

- `start() -> {ok, Pid} | {error, What}`
[page 39] Starts the code server.

- `start(Flags) -> {ok, Pid} | {error, What}`
[page 39] Starts the code server.
- `start_link() -> {ok, Pid} | {error, What}`
[page 39] Starts and links to the code server.
- `start_link(Flags) -> {ok, Pid} | {error, What}`
[page 39] Starts and links to the code server.
- `set_path(DirList) -> true | {error, What}`
[page 40] Sets the code server search path.
- `get_path() -> Path`
[page 40] Returns the current path of the code server.
- `add_path(Dir) -> true | {error, What}`
[page 40] Add a directory to the end of path.
- `add_pathz(Dir) -> true | {error, What}`
[page 40] Add a directory to the end of path.
- `add_patha(Dir) -> true | {error, What}`
[page 40] Adds a directory to the beginning of path.
- `add_paths(DirList) -> ok`
[page 40] Adds directories to the end of path.
- `add_pathsz(DirList) -> ok`
[page 40] Adds directories to the end of path.
- `add_pathsa(DirList) -> ok`
[page 41] Adds directories to the beginning of path.
- `del_path(NameDir) -> true | false | {error, What}`
[page 41] Deletes a directory from the path.
- `replace_path(Name, Dir) -> true | {error, What}`
[page 41] Replaces a directory with another in the path.
- `load_file(Module) -> {module, Module} | {error, What}`
[page 41] Loads a module (residing in File).
- `load_abs(File) -> {module, Module} | {error, What}`
[page 41] Loads a module (residing in File).
- `ensure_loaded(Module) -> {module, Module} | {error, What} | {interpret, Module}`
[page 42] Tries to ensure that a module is loaded.
- `delete(Module) -> true | false`
[page 42] Deletes the code in Module.
- `purge(Module) -> true | false`
[page 42] Purges the code in Module.
- `soft_purge(Module) -> true | false`
[page 42] Purges the code in Module if no process uses it.
- `is_loaded(Module) -> {file, Loaded} | false`
[page 42] Tests if Module is loaded.
- `all_loaded() -> [LoadMod]`
[page 43] Gets all loaded modules.
- `load_binary(Module, File, Binary) -> {module, Module} | {error, What}`
[page 43] Loads object code as a binary.

- `stop() -> stopped`
[page 43] Stops the code server.
- `root_dir() -> RootDir`
[page 43] Returns the root directory of the Erlang system.
- `lib_dir() -> LibDir`
[page 43] Returns the library directory.
- `lib_dir(Name) -> LibDir | {error, What}`
[page 43] Returns the directory for name.
- `compiler_dir() -> CompDir`
[page 44] Returns the compiler directory.
- `priv_dir(Name) -> PrivDir | {error, What}`
[page 44] Returns the priv directory for name.
- `get_object_code(Module) -> {Module, Bin, AbsFileName} | error`
[page 44] Gets the object code for a module.
- `objfile_extension() -> Ext`
[page 44] Returns the object code file extension.
- `stick_dir(Dir) -> ok | {error, term()}`
[page 44] Marks a directory as 'sticky'.
- `unstick_dir(Dir) -> ok | {error, term()}`
[page 45] Marks a directory as 'non-sticky'.
- `which(Module) -> WhichFile`
[page 45] Returns the directory to a module.
- `clash() -> ok`
[page 45] Searches for modules with identical names.
- `interpret(Module) -> {module, Module} | {error, What}`
[page 45] Marks a module as being interpreted.
- `interpret_binary(Module, File, Binary) -> {module, Module} | {error, What}`
[page 45] Loads an interpreted module into the interpreter.
- `delete_interpret(Module) -> ok | {error, What}`
[page 45] Do not interpret a module.
- `interpreted() -> Modules`
[page 46] Returns all interpreted modules.
- `interpreted(Module) -> true | false`
[page 46]

disk_log

The following functions are exported:

- `alog(Log, Term) -> ok | {error, Reason}`
[page 48] Asynchronously logs an item
- `balog(Log, Bytes) -> ok | {error, Reason}`
[page 48] Asynchronously logs an item
- `alog_terms(Log, TermList) -> ok | {error, Reason}`
[page 48] Asynchronously logs several items

- `balog_terms(Log, BytesList) -> ok | {error, Reason}`
[page 48] Asynchronously logs several items
- `block(Log)`
[page 49] Blocks a disk log
- `block(Log, QueueLogRecords) -> ok | {error, Reason}`
[page 49] Blocks a disk log
- `change_header(Log, Header) -> ok | {error, Reason}`
[page 49] Changes the head or head_func option for an owner
- `change_notify(Log, Owner, Notify) -> ok | {error, Reason}`
[page 49] Changes the notify option for an owner
- `change_size(Log, Size) -> ok | {error, Reason}`
[page 50] Changes the size of an open disk log
- `chunk(Log, Continuation)`
[page 50] Reads a chunk of objects written to the disk log.
- `chunk(Log, Continuation, N) -> {Continuation2, Terms} | {Continuation2, Terms, Badbytes} | eof | {error, Reason}`
[page 50] Reads a chunk of objects written to the disk log.
- `chunk_step(Log, Continuation, Step) -> {ok, Continuation2} | {error, Reason}`
[page 51] Steps forward or backward among wrap log files
- `close(Log) -> ok | {error, Reason}`
[page 51] Closes a disk log
- `format_error(Error) -> character_list()`
[page 52] Returns an English description of a disk log error reply
- `inc_wrap_file(Log) -> ok | {error, Reason}`
[page 52] Changes to next wrap log file
- `info(Log) -> InfoList | {error, no_such_log}`
[page 52] Returns a list of {Tag, Value} pairs describing the disk log
- `log(Log, Term) -> ok | {error, Reason}`
[page 53] Logs an item
- `blog(Log, Bytes) -> ok | {error, Reason}`
[page 53] Logs an item
- `log_terms(Log, TermList) -> ok | {error, Reason}`
[page 54] Logs several items
- `blog_terms(Log, BytesList) -> ok | {error, Reason}`
[page 54] Logs several items
- `open(ArgL) -> OpenRet`
[page 54] Opens a disk log file
- `reopen(Log, File)`
[page 57] Reopens a disk log, and saves the old log
- `reopen(Log, File, Head)`
[page 57] Reopens a disk log, and saves the old log
- `breopen(Log, File, BHead) -> ok | {error, Reason}`
[page 57] Reopens a disk log, and saves the old log
- `sync(Log) -> ok | {error, Reason}`
[page 57] Flushes contents of the log to the disk

- `truncate(Log)`
[page 58] Truncates a disk log
- `truncate(Log, Head)`
[page 58] Truncates a disk log
- `btruncate(Log, BHead) -> ok | {error, Reason}`
[page 58] Truncates a disk log
- `unblock(Log) -> ok | {error, Reason}`
[page 58] Unblocks a disk log

erl_boot_server

The following functions are exported:

- `start(Slaves) -> {ok, Pid} | {error, What}`
[page 59] Starts the boot server.
- `start_link(Slaves) -> {ok, Pid} | {error, What}`
[page 59] Starts the boot server and links the caller.
- `add_slave(Slave) -> ok | {error, What}`
[page 59] Adds a slave to the list of allowed slaves.
- `delete_slave(Slave) -> ok | {error, What}`
[page 60] Deletes a slave from the list of allowed slaves.
- `which_slaves() -> Slaves`
[page 60] Returns the current list of allowed slave hosts.

erl_ddll

The following functions are exported:

- `start() -> {ok, Pid} | {error, Reason}`
[page 61] Starts the server.
- `start_link() -> {ok, Pid} | {error, Reason}`
[page 61] Starts the server and links it to the calling process.
- `stop() -> ok`
[page 61] Stops the server.
- `load_driver(Path, Name) -> ok | {error, ErrorDescriptor}`
[page 61] Loads a driver.
- `unload_driver(Name) -> ok | {error, ErrorDescriptor}`
[page 61] Loads a driver.
- `loaded_drivers() -> {ok, DriverList}`
[page 62] Loads a driver.
- `format_error(ErrorDescriptor) -> string()`
[page 62] Formats an error descriptor

erl_prim_loader

The following functions are exported:

- `start(Id, Loader, Hosts) -> {ok, Pid} | {error, What}`
[page 64] Starts the Erlang low level loader.
- `get_file(File) -> {ok, Bin, FullName} | error`
[page 64] Gets a file.
- `get_path() -> {ok, Path}`
[page 65] Gets the path set in the loader.
- `set_path(Path) -> ok`
[page 65] Sets the path of the loader.

erlang

The following functions are exported:

- `abs(Number)`
[page 68]
- `apply({Module, Function}, ArgumentList)`
[page 68]
- `apply(Module, Function, ArgumentList)`
[page 68]
- `atom_to_list(Atom)`
[page 68]
- `binary_to_list(Binary)`
[page 68]
- `binary_to_list(Binary, Start, Stop)`
[page 68]
- `binary_to_term(Binary)`
[page 69]
- `erlang:cancel_timer(Ref)`
[page 69]
- `erlang:check_process_code(Pid, Module)`
[page 69]
- `concat_binary(ListOfBinaries)`
[page 69]
- `date()`
[page 69]
- `erlang:delete_module(Module)`
[page 70]
- `erlang:demonitor(Ref)`
[page 70]
- `erlang:disconnect_node(Node)`
[page 70]

- `element(N, Tuple)`
[page 70]
- `erase()`
[page 70]
- `erase(Key)`
[page 70]
- `exit(Reason)`
[page 71]
- `exit(Pid, Reason)`
[page 71]
- `fault(Reason)`
[page 71]
- `fault(Reason, Args)`
[page 71]
- `float(Number)`
[page 72]
- `erlang:fun_info(Fun)`
[page 72]
- `erlang:fun_info(Fun, Item)`
[page 72]
- `erlang:fun_to_list(Fun)`
[page 72]
- `float_to_list(Float)`
[page 72]
- `get()`
[page 73]
- `get(Key)`
[page 73]
- `erlang:get_cookie()`
[page 73]
- `get_keys(Value)`
[page 73]
- `group_leader()`
[page 73]
- `group_leader(Leader, Pid)`
[page 73]
- `halt()`
[page 73]
- `halt(Status)`
[page 74]
- `erlang:hash(Term, Range)`
[page 74]
- `hd(List)`
[page 74]
- `erlang:info(What)`
[page 74]

- `integer_to_list(Integer)`
[page 74]
- `is_alive()`
[page 74]
- `is_process_alive(Pid)`
[page 74]
- `length(List)`
[page 74]
- `link(Pid)`
[page 75]
- `list_to_atom(CharIntegerList)`
[page 75]
- `list_to_binary(ListOfIntegers)`
[page 75]
- `list_to_float(AsciiIntegerList)`
[page 75]
- `list_to_integer(AsciiIntegerList)`
[page 75]
- `list_to_pid(AsciiIntegerList)`
[page 75]
- `list_to_tuple(List)`
[page 76]
- `erlang:load_module(Module, Binary)`
[page 76]
- `erlang:localtime()`
[page 76]
- `erlang:localtime_to_universaltime(DateTime)`
[page 76]
- `make_ref()`
[page 77]
- `erlang:module_loaded(Module)`
[page 77]
- `erlang:monitor(Type, Item)`
[page 77]
- `monitor_node(Node, Flag)`
[page 77]
- `node()`
[page 78]
- `node(Arg)`
[page 78]
- `nodes()`
[page 78]
- `now()`
[page 78]
- `open_port(PortName, PortSettings)`
[page 78]

- `pid_to_list(Pid)`
[page 80]
- `erlang:port_info(Port, Item)`
[page 80]
- `erlang:ports()`
[page 81]
- `erlang:pre_loaded()`
[page 81]
- `erlang:process_display(Pid, Type)`
[page 81]
- `process_flag(Flag, Option)`
[page 81]
- `process_flag(Pid, Flag, Option)`
[page 82]
- `process_info(Pid)`
[page 82]
- `process_info(Pid, Item)`
[page 83]
- `processes()`
[page 83]
- `erlang:purge_module(Module)`
[page 83]
- `put(Key, Value)`
[page 84]
- `register(Name, Pid)`
[page 84]
- `registered()`
[page 84]
- `erlang:resume_process(Pid)`
[page 84]
- `round(Number)`
[page 85]
- `self()`
[page 85]
- `erlang:send_after(Time, Pid, Msg)`
[page 85]
- `erlang:set_cookie(Node, Cookie)`
[page 85]
- `setelement(Index, Tuple, Value)`
[page 85]
- `size(Item)`
[page 85]
- `spawn(Fun)`
[page 86]
- `spawn(Node, Fun)`
[page 86]

- `spawn(Module, Function, ArgumentList)`
[page 86]
- `spawn(Node, Module, Function, ArgumentList)`
[page 86]
- `spawn_link(Fun)`
[page 86]
- `spawn_link(Node, Fun)`
[page 86]
- `spawn_link(Module, Function, ArgumentList)`
[page 86]
- `spawn_link(Node, Module, Function, ArgumentList)`
[page 87]
- `spawn_opt(Module, Function, ArgumentList, Options)`
[page 87]
- `split_binary(Binary, Pos)`
[page 87]
- `erlang:start_timer(Time, Pid, Msg)`
[page 88]
- `statistics(Type)`
[page 88]
- `erlang:suspend_process(Pid)`
[page 88]
- `erlang:system_flag(Flag, Value)`
[page 88]
- `term_to_binary(Term)`
[page 89]
- `throw(Any)`
[page 89]
- `time()`
[page 89]
- `tl(List)`
[page 89]
- `erlang:trace(PidSpec, How, Flaglist)`
[page 89]
- `erlang:trace_info(PidOrFunc, Item)`
[page 91]
- `erlang:trace_pattern(MFA, MatchSpec)`
[page 92]
- `trunc(Number)`
[page 93]
- `tuple_to_list(Tuple)`
[page 93]
- `erlang:universaltime()`
[page 93]
- `erlang:universaltime_to_localtime(DateTime)`
[page 93]

- `unlink(Pid)`
[page 93]
- `unregister(Name)`
[page 94]
- `whereis(Name)`
[page 94]

error_handler

The following functions are exported:

- `undefined_function(Module, Func, ArgList) -> term()`
[page 95] Called when an undefined function is encountered
- `undefined_lambda(Module, Fun, ArgList) -> term()`
[page 95] Called when an undefined lambda (fun) is encountered

error_logger

The following functions are exported:

- `start() -> {ok, Pid} | {error, What}`
[page 97] Starts the error logger event manager.
- `start_link() -> {ok, Pid} | {error, What}`
[page 97] Starts the error logger event manager.
- `error_report(Report) -> ok`
[page 97] Sends a standard error report event to the error logger.
- `error_report(Type,Report) -> ok`
[page 98] Sends a user defined error report type event.
- `info_report(Report) -> ok`
[page 98] Sends an information report to the error logger.
- `info_report(Type,Report) -> ok`
[page 98] Sends a user defined information report type event.
- `error_msg(Format) -> ok`
[page 99] Sends an error event to the error logger.
- `error_msg(Format,Args) -> ok`
[page 99] Sends an error event to the error logger.
- `format(Format,Args) -> ok`
[page 99] Sends an error event to the error logger.
- `info_msg(Format) -> ok`
[page 99] Sends an information event to the error logger.
- `info_msg(Format,Args) -> ok`
[page 99] Sends an information event to the error logger.
- `tty(Flag) -> ok`
[page 99] Enables or disables error printouts to the tty.

- `logfile(Request) -> ok | FileName | {error, What}`
[page 99] Enables or disables error printouts to a file.
- `add_report_handler(Module) -> ok | Other`
[page 100] Adds a new event handler to the error logger.
- `add_report_handler(Module,Args) -> ok | Other`
[page 100] Adds a new event handler to the error logger.
- `delete_report_handler(Module) -> Return | {error, What}`
[page 100] Deletes an error report handler.
- `swap_handler(ToHandler) -> ok`
[page 100] Swap from a primitive first handler to a standard event handler

file

The following functions are exported:

- `change_group(Filename, Gid)`
[page 102] Change owner for a file
- `change_owner(Filename, Uid)`
[page 102] Change owner of a file
- `change_owner(Filename, Uid, Gid)`
[page 102] Change owner for a file
- `change_time(Filename, Mtime)`
[page 102] Change the modification time for a file
- `change_time(Filename, Mtime, Atime)`
[page 102] Change the modification time for a file
- `close(IoDevice)`
[page 102] Close a file
- `consult(Filename)`
[page 102] Read Erlang terms from a file
- `del_dir(DirName)`
[page 103] Delete a directory
- `delete(Filename)`
[page 103] Delete a file
- `eval(Filename)`
[page 103] Evaluate expressions in a file
- `file_info(Filename)`
[page 103] Get information about a file
- `format_error(ErrorDescriptor)`
[page 104] Returns an English description of an error term
- `get_cwd()`
[page 104] Get the current working directory
- `get_cwd(Drive)`
[page 104] Get the current working directory for the drive specified
- `list_dir(DirName)`
[page 105] List files in a directory

- `make_dir(DirName)`
[page 105] Make a directory
- `make_link(Existing, New)`
[page 105] Make a hard link to a file
- `make_symlink(Name1, Name2)`
[page 105] Make a symbolic link to a file or directory
- `open(Filename, ModeList)`
[page 106] Open a file
- `path_consult(Path, Filename)`
[page 107] Read Erlang terms from a file
- `path_eval(Path, Filename)`
[page 107] Evaluate expressions in a file
- `path_open(Path, Filename, Mode)`
[page 107] Open a file for access
- `position(IoDevice, Location)`
[page 107] Set position in a file
- `pread(IoDevice, Location, Number)`
[page 108] Write to a file at a certain position
- `pwrite(IoDevice, Location, Bytes)`
[page 108] Write to a file at a certain position
- `read(IoDevice, Number)`
[page 108] Read from a file
- `read_file(Filename)`
[page 108] Read a file
- `read_file_info(Filename)`
[page 109] Get information about a file
- `read_link(Linkname)`
[page 110] See what a link is pointing to
- `read_link_info(Filename)`
[page 110] Get information about a link or file
- `rename(Source, Destination)`
[page 110] Rename a file
- `set_cwd(DirName)`
[page 111] Set the current working directory
- `sync(IoDevice)`
[page 111] Synchronizes the in-memory state of a file with that on the physical medium
- `truncate(IoDevice)`
[page 111] Truncate a file
- `write(IoDevice, Bytes)`
[page 111] Write to a file
- `write_file(Filename, Binary)`
[page 111] Write a file
- `write_file_info(Filename, FileInfo)`
[page 112] Change file information

gen_tcp

The following functions are exported:

- `accept(ListenSocket) -> {ok, Socket} | {error, Reason}`
[page 116] Accepts an incoming connection request on a listen socket.
- `accept(ListenSocket, Timeout) -> {ok, Socket} | {error, Reason}`
[page 116] Accepts an incoming connection request on a listen socket.
- `close(Socket) -> ok | {error, Reason}`
[page 116] Closes an TCP socket
- `connect(Address, Port, Options) -> {ok, Socket} | {error, Reason}`
[page 116] Connects to a TCP port.
- `connect(Address, Port, Options, Timeout) -> {ok, Socket} | {error, Reason}`
[page 116] Connects to a TCP port.
- `controlling_process(Socket, NewOwner) -> ok | {error, eperm}`
[page 117] Assigns a new controlling process to a socket
- `listen(Port, Options) -> {ok, Socket} | {error, Reason}`
[page 117] Sets up a socket which listen on Port
- `recv(Socket, Length) -> {ok, Packet} | {error, Reason}`
[page 117] Receives a packet from a passive socket
- `recv(Socket, Length, Timeout)`
[page 117] Receives a packet from a passive socket
- `send(Socket, Packet) -> ok | {error, Reason}`
[page 118] Sends a packet

gen_udp

The following functions are exported:

- `close(Socket) -> ok | {error, Reason}`
[page 119] Close Socket.
- `controlling_process(Socket, NewOwner) ->`
[page 119] Change controlling process of a Socket.
- `open(Port) -> {ok, Socket } | { error, Reason }`
[page 119] Associates a UDP port number with the process calling it.
- `open(Port, Options) -> {ok, Socket } | { error, Reason }`
[page 119] Associates a UDP port number with the process calling it.
- `recv(Socket, Length) -> {ok,{Address, Port, Packet}} | {error, Reason}`
[page 120] Receives a packet from a passive socket
- `recv(Socket, Length, Timeout)`
[page 120] Receives a packet from a passive socket
- `send(S,Address,Port,Packet) -> ok | {error, Reason}`
[page 120] Sends a packet to a specified Address and Port (from port associated with Id).

global

The following functions are exported:

- `del_lock(Id)`
[page 121] Deletes the lock Id
- `del_lock(Id, Nodes) -> void()`
[page 121] Deletes the lock Id
- `notify_all_name(Name, Pid1, Pid2) -> none`
[page 122] Name resolving function that notifies both Pids
- `random_exit_name(Name, Pid1, Pid2) -> Pid1 | Pid2`
[page 122] Name resolving function that kills one Pid
- `random_notify_name(Name, Pid1, Pid2) -> Pid1 | Pid2`
[page 122] Name resolving function that notifies one Pid
- `register_name(Name, Pid)`
[page 122] Globally registers Pid as Name
- `register_name(Name, Pid, Resolve) -> yes | no`
[page 122] Globally registers Pid as Name
- `registered_names() -> [Name]`
[page 122] Returns all globally registered names
- `re_register_name(Name, Pid)`
[page 123] Atomically re-registers Pid for Name
- `re_register_name(Name, Pid, Resolve) -> void()`
[page 123] Atomically re-registers Pid for Name
- `send(Name, Msg) -> Pid`
[page 123] Sends Msg to the global process Name
- `set_lock(Id)`
[page 123] Sets a lock on the specified nodes
- `set_lock(Id, Nodes)`
[page 123] Sets a lock on the specified nodes
- `set_lock(Id, Nodes, Retries) -> boolean()`
[page 123] Sets a lock on the specified nodes
- `start()`
[page 124] Starts the global name server
- `start_link() -> {ok, Pid} | {error, Reason}`
[page 124] Starts the global name server
- `stop() -> void()`
[page 124] Stops the global name server
- `sync() -> void()`
[page 124] Synchronizes the global name server
- `trans(Id, Fun)`
[page 124] Micro transaction facility
- `trans(Id, Fun, Nodes)`
[page 124] Micro transaction facility
- `trans(Id, Fun, Nodes, Retries) -> Res | aborted`
[page 124] Micro transaction facility

- `unregister_name(Name) -> void()`
[page 124] Unregisters the global name Name
- `whereis_name(Name) -> Pid() | undefined`
[page 124] Returns the Pid of the global process Name

global_group

The following functions are exported:

- `global_groups() -> {OwnGroupName, [OtherGroupName]} | undefined`
[page 126] Returns the global group names
- `info() -> [{state, State}, {own_group_name, atom()}, {own_group_nodes, [Node]}, {synced_nodes, [Node]}, {sync_error, [Node]}, {no_contact, [Node]}, {other_groups, Other_grps}, {monitoring, [pid()]}]`
[page 126] Returns the state of the global group process
- `monitor_nodes(Flag) -> ok`
[page 126] Subscription of node status for nodes in the immediate global group
- `own_nodes() -> [Node] | {error, ErrorMsg}`
[page 126] Returns the global group names
- `registered_names({node, Node}) -> [Name] | {error, ErrorMsg}`
[page 126] Returns all globally registered names
- `registered_names({group, GlobalGroupName}) -> [Name]`
[page 126] Returns all globally registered names
- `send(Name, Msg) -> Pid | {badarg, Msg} | {error, ErrorMsg}`
[page 127] Sends Msg to a registered process Name
- `send({node, Node}, Name, Msg) -> Pid | {badarg, Msg} | {error, ErrorMsg}`
[page 127] Sends Msg to a registered process Name
- `send({group, GlobalGroupName}, Name, Msg) -> Pid | {badarg, Msg} | {error, ErrorMsg}`
[page 127] Sends Msg to a registered process Name
- `sync() -> ok`
[page 127] Synchronizes the immediate global group
- `whereis_name(Name) -> Pid | undefined | {error, ErrorMsg}`
[page 127] Returns the Pid of the global process Name
- `whereis_name({node, Node}, Name) -> Pid | undefined | {error, ErrorMsg}`
[page 127] Returns the Pid of the global process Name
- `whereis_name({group, GlobalGroupName}, Name) -> Pid | undefined | {error, ErrorMsg}`
[page 127] Returns the Pid of the global process Name
- `start()`
[page 128] Starts the global group server
- `start_link() -> {ok, Pid} | {error, Reason}`
[page 128] Starts the global group server
- `stop() -> void()`
[page 128] Stops the global group server

heart

The following functions are exported:

- `start() -> {ok, Pid} | ignore | {error, What}`
[page 129] Starts the heart program.
- `set_cmd(Cmd) -> ok | {error, {bad_cmd, Cmd}}`
[page 130] Sets a temporary reboot command.
- `clear_cmd() -> ok`
[page 130] Clears the temporary boot command.

inet

The following functions are exported:

- `format_error(Tag)`
[page 131] Returns a diagnostic error string.
- `gethostbyaddr(Address) -> {ok, Hostent} | {error, Reason}`
[page 131] Returns a hostent record for the host with the given address
- `gethostbyname(Name) -> {ok, Hostent} | {error, Reason}`
[page 131] Returns a hostent record for the host with the given name
- `gethostbyname(Name, Family) -> {ok, Hostent} | {error, Reason}`
[page 132] Returns a hostent record for the host with the given name
- `gethostname() -> {ok, Name} | {error, Reason}`
[page 132] Returns the local hostname
- `sockname(Socket) -> {ok, {IP, Port}} | {error, Reason}`
[page 132] Returns the local address and port number for a socket.
- `peername(Socket) -> {ok, {Address, Port}} | {error, Reason}`
[page 132] Returns the address and port for the other end of a connection.
- `port(Socket) -> {ok, Number}`
[page 132] Returns the local port number for a socket.
- `close(Socket) -> ok`
[page 132] Closes a socket of any type
- `getaddr(IP, inet) -> {ok, {A1,A2,A3,A4}} | {error, Reason}`
[page 133] Returns the IP-adress for IP
- `setopts(Socket, Options) -> ok | {error, Reason}`
[page 133] Sets one or more options for a socket.

init

The following functions are exported:

- `boot(BootArgs) -> void()`
[page 138] Start the Erlang system.

- `get_arguments()` -> Flags
[page 138] Get all flag arguments.
- `get_argument(Flag)` -> {ok, Values} | error
[page 139] Get values associated with an argument.
- `get_args()` -> [Arg]
[page 139] Get all (non-flag) arguments.
- `restart()` -> void()
[page 139]
- `reboot()` -> void()
[page 139]
- `stop()` -> void()
[page 139]
- `get_status()` -> {InternalStatus, ProvidedStatus}
[page 139] Get status information during system start.
- `script_id()` -> Id
[page 140] Get the identity of the used boot script.

net_adm

The following functions are exported:

- `host_file()`
[page 142]
- `dns_hostname(Host)`
[page 142]
- `localhost()`
[page 142]
- `names()`, `names(Host)`
[page 142]
- `ping(Node)`
[page 142]
- `world()`, `world(verbose)`
[page 142]
- `world_list(Hostlist)`, `world_list(Hostlist, verbose)`
[page 142]

net_kernel

The following functions are exported:

- `kernel_apply(M, F, A)`
[page 144]
- `monitor_nodes(Flag)`
[page 144]
- `allow(NodeList)`
[page 144]

OS

The following functions are exported:

- `cmd(Command) -> string()`
[page 145] Executes Command in a command shell of the target OS.
- `find_executable(Name) -> Filename | false`
[page 145] Returns the absolute filename of a program.
- `find_executable(Name, Path) -> Filename | false`
[page 145] Returns the absolute filename of a program.
- `getenv(VarName) -> Value | false`
[page 145] Returns the Value of the environment variable VarName.
- `getpid() -> Value`
[page 146] Returns the process identifier of the emulator process as a string.
- `type() -> {Osfamily,Osname} | Osfamily`
[page 146] Returns the Osfamily and, in some cases, Osname of the current operating system.
- `version() -> {Major, Minor, Release} | VersionString`
[page 146] Returns the Operating System version.

pg2

The following functions are exported:

- `create(Name) -> void()`
[page 147] Creates a new, empty process group
- `delete(Name) -> void()`
[page 147] Deletes a process group
- `get_closest_pid(Name) -> Pid | {error, Reason}`
[page 147] Common dispatch function
- `get_members(Name) -> [Pid] | {error, Reason}`
[page 147] Returns all processes in a group
- `get_local_members(Name) -> [Pid] | {error, Reason}`
[page 148] Returns all local processes in a group
- `join(Name, Pid) -> ok | {error, Reason}`
[page 148] Joins a process to a group
- `leave(Name, Pid) -> ok | {error, Reason}`
[page 148] Makes a process leave a group
- `which_groups() -> [Name]`
[page 148] Returns a list of all known groups
- `start()`
[page 148] Starts the pg2 server
- `start_link() -> {ok, Pid} | {error, Reason}`
[page 148] Starts the pg2 server

rpc

The following functions are exported:

- `start()`
[page 149]
- `stop()`
[page 149]
- `call(Node, Module, Function, Args)`
[page 149]
- `cast(Node, Module, Function, Args)`
[page 149]
- `block_call(Node, Mod, Fun, Args)`
[page 149]
- `server_call(Node, Name, ReplyWrapper, Msg)`
[page 150]
- `abcast(Name, Mess)`
[page 150]
- `abcast(Nodes, Name, Mess)`
[page 150]
- `sbcast(Name, Msg)`
[page 150]
- `sbcast(Nodes, Name, Msg)`
[page 150]
- `eval_everywhere(Mod, Fun, Args)`
[page 150]
- `eval_everywhere(Nodes, Mod, Fun, Args)`
[page 150]
- `multicall(M, F, A)`
[page 150]
- `multicall(Nodes, M, F, A)`
[page 151]
- `multi_server_call(Name, Msg)`
[page 151]
- `multi_server_call(Nodes, Name, Msg)`
[page 151]
- `safe_multi_server_call(Name, Msg)`
[page 151]
- `safe_multi_server_call(Nodes, Name, Msg)`
[page 151]
- `async_call(Node, Mod, Fun, Args)`
[page 152]
- `yield(Key)`
[page 152]
- `nb_yield(Key)`
[page 152]

- `parallel_eval(ListOfTuples)`
[page 152]
- `pmap({M, F}, Extraargs, List)`
[page 152]
- `pinfo(Pid)`
[page 152]
- `pinfo(Pid, Item)`
[page 152]

seq_trace

The following functions are exported:

- `set_token(Component, ComponentValue) -> {Component, PreviousValue}`
[page 153] Sets the individual Component of the trace token.
- `set_token(Token) -> PreviousToken`
[page 154] Sets the trace token to Value.
- `get_token(Component) -> {Component, ComponentValue}`
[page 154] Returns the ComponentValue of the trace token component Component.
- `get_token() -> TraceToken`
[page 154] Returns the value of the trace token.
- `print(TraceInfo) -> void`
[page 154] Puts the Erlang term TraceInfo into the sequential trace output.
- `reset_trace() -> void`
[page 155] Stops all sequential tracing on the Erlang node.
- `set_system_tracer(ProcessOrPortId) -> PreviousId`
[page 155] Sets the system tracer.
- `get_system_tracer() -> pid() | port() | false`
[page 155] Returns the pid() or port() of the current system tracer.

user

The following functions are exported:

- `start() -> void()`
[page 161] Starts the standard I/O system.

wrap_log_reader

The following functions are exported:

- `chunk(Continuation)`
[page 162] Reads a chunk of objects written to a wrap log.

- `chunk(Continuation, N) -> {Continuation2, Terms} | {Continuation2, Terms, Badbytes} | {Continuation2, eof} | {error, Reason}`
[page 162] Reads a chunk of objects written to a wrap log.
- `close(Continuation) -> ok`
[page 163] Closes a log
- `open(Filename) -> OpenRet`
[page 163] Opens a log file
- `open(Filename, N) -> OpenRet`
[page 163] Opens a log file

app

No functions are exported

config

No functions are exported

kernel (Application)

The `kernel` application is the first application started, and it is one of two mandatory applications. The Kernel application contains the following services:

- `application_controller`
- `auth`
- `code`
- `disk_log`
- `erl_boot_server`
- `erl_ddll`
- `error_logger`
- `file`
- `global_group`
- `global_name_server`
- `net_kernel`
- `os`
- `rpc`
- `pg2`
- `timer`
- `user`

It is possible to synchronize a set of Erlang nodes. One can specify for a node to wait a specified amount of time for other nodes to become alive.

Error Logger Event Handlers

Two error logger event handlers are defined in the kernel application. These are described in `error_logger(3)`.

Configuration

The following configuration parameters are defined for the kernel application. See `application(3)` for more information about configuration parameters.

`distributed = [Distrib] <optional>` Specifies which applications are distributed and on which nodes they may execute. In this parameter:

- `Distrib = {ApplName, Nodes} | {ApplName, Time, Nodes}`
- `ApplName = atom()`
- `Time = integer() > 0`
- `Nodes = [node() | {node(), ..., node()}]`

These parameters are described in `application(3)`.

`permissions = [Perm] <optional>` Specifies the default permission for applications when they are started. In this parameter:

- `Perm = {ApplName, Bool}`
- `ApplName = atom()`
- `Bool = boolean()`

`error_logger = Value <optional>` Value is one of:

`tty` All standard error reports are written to `stdio`. This is the default option.

`{file, FileName}` All standard error reports are written to the file `FileName`, where `FileName` is a string.

`false` No error logger handler is installed.

`global_groups = [GroupName, [Node]] <optional>` Specifies the groups of nodes which will have their own global name space. In this parameter:

- `GroupName = atom()`
- `Node = atom()`

These parameters are described in `global_group(3)`.

`inet_parse_error_log = LogMode <optional>` LogMode is one of:

`silent` No `error_logger` messages are generated when erroneous lines are found and skipped in the various configuration files. The default if the variable is not set is that erroneous lines are reported via the `error_logger`.

`net_ticktime = TickTime <optional>` Specifies the `net_kernel` tick time.

`TickTime` is given in seconds. Once every `TickTime / 4` second, all connected nodes are ticked (if anything else has been written to a node) and if nothing has been received from another node within the last four (4) tick times that node is considered to be down. This ensures that nodes which are not responding, for reasons such as hardware errors, are considered to be down.

The time `T`, in which a node that is not responding is detected, is calculated as:

`MinT < T < MaxT` where

```
MinT = TickTime - TickTime / 4
MaxT = TickTime + TickTime / 4
```

`TickTime` is by default 60 (seconds). Thus, $45 < T < 75$ seconds.

Note: All communicating nodes should have the same `TickTime` value specified.

Note: Normally, a terminating node is detected immediately.

`sync_nodes_mandatory = [NodeName] <optional>` Specifies which other nodes must be alive in order for this node to start properly. If some node in this list does not start within the specified time, this node will not start either. If this parameter is undefined, it defaults to the empty list.

`sync_nodes_optional = [NodeName] <optional>` Specifies which other nodes can be alive in order for this node to start properly. If some node in this list does not start within the specified time, this node starts anyway. If this parameter is undefined, it defaults to the empty list.

`sync_nodes_timeout = integer() | infinity <optional>` Specifies the amount of time (in milliseconds) this node will wait for the mandatory and optional nodes to start. If this parameter is undefined, no node synchronization is performed. This option also makes sure that global is synchronized.

`start_ddll = true | false <optional>` Starts the `ddll_server` if the parameter is true (see `erl_ddll(3)`). This parameter should be set to true in an embedded system which uses this service.
The default value is `false`.

`start_dist_ac = true | false <optional>` Starts the `dist_ac` server if the parameter is true (see `application(3)`). This parameter should be set to true for systems that use distributed applications.
The default value is `false`. If this parameter is undefined, the server is started if the parameter `distributed` is set.

`start_boot_server = true | false <optional>` Starts the `boot_server` if the parameter is true (see `erl_boot_server(3)`). This parameter should be set to true in an embedded system which uses this service.
The default value is `false`.

`boot_server_slaves = [SlaveIP] <optional>` If the `start_boot_server` configuration parameter is true, this parameter can be used to initialize `boot_server` with a list of slave IP addresses. `SlaveIP = string() | atom | { integer(),integer(),integer(),integer() }`
where $0 \leq \text{integer}() \leq 255$.
Examples of `SlaveIP` in atom, string and tuple form are:
`'150.236.16.70'`, `"150,236,16,70"`, `{150,236,16,70}`.
The default value is `[]`.

`start_disk_log = true | false <optional>` Starts the `disk_log_server` if the parameter is true (see `disk_log(3)`). This parameter should be set to true in an embedded system which uses this service.
The default value is `false`.

`start_os = true | false <optional>` Starts the `os_server` if the parameter is true (see `os(3)`). This parameter should be set to true in an embedded system which uses this service.
The default value is `false`.

`start_pg2 = true | false <optional>` Starts the `pg2` server (see `pg2(3)`) if the parameter is true. This parameter should be set to true in an embedded system which uses this service.
The default value is `false`.

`start_timer = true | false <optional>` Starts the `timer_server` if the parameter is true (see `timer(3)`). This parameter should be set to true in an embedded system which uses this service.
The default value is `false`.

`keep_zombies = integer() <optional>` Sets the value of the system flag `keep_zombies`.
The default value is 0.

See Also

`application(3)`, `auth(3)`, `code(3)`, `disk_log(3)`, `erl_ddll(3)`, `erl_boot_server(3)`,
`error_logger(3)`, `file(3)`, `global(3)`, `global_group(3)`, `net_kernel(3)`, `os(3)`, `pg2(3)`, `rpc(3)`,
`timer(3)`, `user(3)`

application (Module)

This module contains functions for controlling applications (eg. starting and stopping applications), and functions to access information about any application, (eg. configuration parameters)

All applications are started by the `application_controller` process. Each application has an `application_master` process. This process monitors the application and reports to the application controller if the application terminates.

An application can be started locally or distributed. A distributed application is started on one of several nodes while a local application is always started on the current node.

The local applications are controlled by the application controller. The distributed applications are controlled by another process, called the distributed application controller (`dist_ac`). The distributed application controller on different nodes monitor each other. Therefore, if a node goes down, the distributed applications on that node will be automatically re-started on one of the remaining nodes.

The distributed application controller is not started by default. Systems that use distributed applications must set the configuration parameter `start_dist_ac` in `kernel`.

Exports

```
get_all_env()
get_all_env(Application) -> Env
```

Types:

- Application = atom()
- Env = [{Key, Value}]
- Key = atom()
- Value = term()

Retrieves the values of the application's configuration parameters. If `Application` is not specified, then the configuration parameters for the application which executes the call are returned.

```
get_all_key()
get_all_key(Application) -> {ok, Keys} | undefined
```

Types:

- Application = atom()
- Keys = [{Key, Value}]
- Key = atom()
- Value = term()

Retrieves all the keys from the application's resource file, `Application.app`. If `Application` is not specified, then the keys for the application which executes the call are returned.

```
get_application()
get_application(Pid | Module) -> {ok, Application} | undefined
```

Types:

- Pid = pid()
- Module = atom()
- Application = atom()

Retrieves the name of the application where the process `Pid` executes. If `Pid` is not specified, `self()` is used. If an atom is given the name of the application which contains the module will be returned, or `undefined`.

```
get_env(Key)
get_env(Application, Key) -> {ok, Value} | undefined
```

Types:

- Application = atom()
- Key = atom()
- Value = term()

Retrieves the value of an application's configuration parameter. If `Application` is not specified, the parameter for the application which executes the call is retrieved.

```
get_key(Key)
get_key(Application, Key) -> {ok, Value} | undefined
```

Types:

- Application = atom()
- Key = atom()
- Value = term()

Retrieves the key from the application's resource file, `Application.app`. If `Application` is not specified, then the key for the application which executes the call is returned.

```
load(Application)
load(Application, DistNodes) -> ok | {error, Reason}
```

Types:

- Application = atom() | appl_descr()
- DistNodes = {Name, Nodes} | {Name, Time, Nodes} | default
- appl_descr() = {application, Name, [appl_opt()]}
- Name = atom()
- Time = integer() > 0
- Nodes = [node() | {node(), ..., node()}]
- appl_opt() = {description, string()} | {vsn, vsn()} | {modules, [{atom(), vsn()}]} | {registered, [atom()]} | {applications, [atom()]} | {env, [{atom(), term()}]} | {mod, {Mod, StartArgs}}

- `vsn() = string()`

If the name of the application is given, the application controller searches the current path (the same as the code path) for a file called `Application.app`.

Note: This file must contain the `appl_descr()` (written in plain text, with a dot and space after the term).

`description` and `version` - Contains information about an application that can be retrieved by calling `application:loaded_applications/0`.

`modules` - Lists the modules that this application introduces.

`registered` is a list of the registered names that this application uses for its own processes.

`applications` - Lists of other applications that must be started before this one.

`env` is a list of configuration parameters. *Note:* The definitions in this list may be altered by definitions in the system configuration file, specified by the command line argument `-config`. They can also be altered directly from the command line, by giving `-Name Par Value`.

`mod` is the application call back module. `Mod:start(StartType, StartArgs)` is called when the application is started. Refer to the call back function `start/2`.

The `DistNodes` parameter will override the value of the application in the kernel configuration parameter `distributed`. The data structure specifies a list of nodes where the application `Name` may execute. If the nodes are specified in a tuple, the order of where to start the application will be undefined. If a node crashes and `Time` has been specified, then the application controller will wait for `Time` milliseconds before attempting to restart the application on another node. If `Time` is not specified, it will default to 0. If a node goes down, the application will be restarted immediately on another node. If `DistNodes` is `default`, the value in the configuration parameter `distributed` will be used.

`loaded_applications() -> [{Name, Description, Version}]`

Types:

- `Name = atom()`
- `Description = string()`
- `Version = string()`

This function returns a list of applications which are loaded in the system. `Description` and `Version` are as defined in the application specification.

`permit(Application, Bool) -> ok | {error, Reason}`

Types:

- `Name = atom()`
- `Bool = bool()`

This function changes an application's permission to run on the node, or vice versa. If the permission of a locally running application is set to `false`, the application will be stopped. When the permission is set to `true`, the local application will be started. If the permission of a running, distributed application is set to `false`, the application will be moved to another node where it may run, if a node is available.

The application must be loaded before the `permit` function can be called.

This function does not return until the application is either started, stopped or successfully moved to another node. However, in some cases where permission is set to `true` the function may return `ok` even though the application itself has not started. This is true when an application cannot start because it has dependencies on applications which have not yet been started. When these applications are started the dependent application will also be started.

By default, all applications are loaded with permission `true` on all nodes. The permission is configurable with the parameter `permissions` in `kernel`.

```
start(Application)
start(Application, Type) -> ok | {error, Reason}
```

Types:

- Application = atom()
- Type = permanent | transient | temporary

This function starts an application. If the application is not loaded, the application controller will first try to load it, as if `application:load(Application)` was called.

The Type specifies what happens if the application dies.

- If a permanent application dies, all other applications are also terminated.
- If a transient application dies normally, this is reported and no other applications are terminated. If a transient application dies abnormally, all other applications are also terminated.
- If a temporary application dies this is reported and no other applications are terminated. In this way, an application can run in test mode, without disturbing the other applications.

Default value for Type is `temporary`.

```
start_type() -> normal | local | {takeover, node()} | {failover, node()}
```

This function returns the type of application start which is executing.

`normal` is returned when an application is starting and the below circumstances have not occurred.

`local` is returned if a supervised process restarts due to abnormal exit or if no start is running at the time of request.

`{takeover, Node}` is returned if the application is requested to move to another node either due to a call to `takeover/2` or when a node with higher priority to run the application is restarted.

`{failover, Node}` is returned if the application is restarted due to the Node crashing where the application was previously executing.

```
stop(Application) -> ok
```

Types:

- Application = atom()

This function stops a running application. If the application was distributed, no other node will restart it.

```
takeover(Application, Type) -> {ok, Pid} | {error, Reason}
```

Types:

- Application = atom()
- Type = permanent | transient | temporary

This function moves a distributed application which executes on another node Node to the current node. The application is started by calling Mod:start({takeover, Node}, StartArgs) before the application is stopped on the other node. This makes it possible to transfer application specific data from a currently running application to a new node. When the application start function returns, the application on a Node is stopped. This means that two instances of the application may be running on two different nodes at one time. If this is not acceptable, parts of the application on the old node (Node) may be shut down when the new node starts the application. *Note:* that the old application must not be stopped entirely (i.e. application:stop/1 must not be called on the old node). The main supervisor, must still be alive.

```
which_applications() -> [{Name, Description, Version}]
```

Types:

- Name = atom()
- Description = string()
- Version = string()

Returns a list of the applications which are running in the system. Description and Version are as defined in the application specification.

Call back Module

The following functions are exported from an application call back module.

Exports

```
Module:config_change(Changed, New, Removed) -> ok
```

Types:

- Changed = [{Parameter, NewValue}]
- New = [{Parameter, Value}]
- Removed = [Parameter]
- Parameter = atom()

- NewValue = term()
- Value = term()

After an installation of a new release all started applications on a node are notified of the changed, new and removed configuration parameters. The unchanged configuration parameters are not affected and therefore the function is not evaluated for applications which have unchanged configuration parameters between the old and new releases.

`Module:start(Type, ModuleStartArgs) -> {ok, Pid} | {ok, Pid, State} | {error, Reason}`

Types:

- Type = normal | {takeover, node()} | {failover, node()}
- ModuleStartArgs = term()
- Pid = pid()
- State = state()

This function starts a primary application. Normally, this function starts the main supervisor of the primary application.

If Type is {takeover, Node}, it is a distributed application which is running on the Node. If the application does not have the start-phases key defined in the application's resource file, the application will be stopped by the application controller after this call returns (see `start-phase/3`) This makes it possible to transfer the internal state from the running application to the one to be started. This function must not stop the application on Node, but it may shut down parts of it. For example, instead of stopping the application, the main supervisor may terminate all its children.

If Type is {failover, Node}, the application will be restarted due to a crash of the node where the application was previously executing.

{failover, node()} is valid only if the `start_phases` key is defined in the applications resource file. Otherwise the type is set to `normal` at failover.

The `ModuleStartArgs` parameter is specified in the application resource file (.app), as `{mod, {Module, ModuleStartArgs}}`.

`State` is any term. It is passed to `Module:stop/1`. If no `State` is returned, [] is used.

`Module:start_phase(Phase, Type, PhaseStartArgs) -> ok | {error, Reason}`

Types:

- Phase = atom()
- Type = normal | {takeover, node()} | {failover, node()}
- PhaseStartArgs = term()
- Pid = pid()
- State = state()

This function starts a application in the phase `Phase`. It is called by default only for a primary application and not for the included applications, refer to User's Guide chapter 'Design Principles' regarding incorporating included applications.

The `PhaseStartArgs` parameter is specified in the application's resource file (.app), as `{start_phases, [{Phase, PhaseStartArgs}]}`, the `Module` as `{mod, {Module, ModuleStartArgs}}`.

This call back function is only valid for applications with a defined `start_phases` key. This function will be called once per Phase.

If Type is {takeover, Node}, it is a distributed application which runs on the Node. When this call returns for the last start phase, the application on Node will be stopped by the application controller. This makes it possible to transfer the internal state from the running application. When designing the start phase function it is imperative that the application is not allowed to terminate the application on node. However, it is possible to partially shut it down for eg. the main supervisor may terminate all the application's children.

If Type is {failover, Node}, due to a crash of the node where the application was previously executing, the application will restart.

`Module:stop(State) -> void()`

Types:

- State = state()

This function is called when the application has stopped, either because it crashed, or because someone called `application:stop`. It cleans up after the `Module:start/2` function.

State is the state that was returned from `Mod:start/2`, or [] if no state was returned.

See Also

`kernel(3)`

auth (Module)

Authentication determines which nodes are allowed to communicate with each other. In a network of different Erlang nodes, it is built into the system at the lowest possible level. Each node has its `Magic Cookie`, which is an Erlang atom.

Whenever a message is transferred from one node to another, it is accompanied by the `Magic Cookie` of the receiving node. For example, a message transferred from node A to node B is accompanied by what node A believes to be the `Magic Cookie` of node B.

When the message arrives at node B, the runtime system immediately checks that the accompanying cookie is the right one. If it is, the message is passed on in the normal way. If it is not, the message is transformed into a `badcookie` message, which is sent to the system process `net_kernel`. By default, the `net_kernel` process passes the message to the registered process `auth`, which is then responsible for taking the appropriate action for the unauthorized message. In the standard system, the default action is to shut down connection to that node.

At start-up, the first action of the standard `auth` server is to read a file named `$HOME/erlang.cookie`. An atom is created from the contents of this file and the cookie of the node is set to this atom with the use of `erlang:set_cookie(node(), CookieAtom)`.

If the file does not exist, it is created. The UNIX permissions mode of the file is set to octal 400 (read-only by owner) and filled with a random string. For this reason, the same user, or group of users with identical cookie files, can have Erlang nodes which can communicate freely and without interference from the `Magic Cookie` system. Users who want to run nodes on separate file systems must be certain that their cookie files are identical on the different file systems.

Initially, each node has a random atom assigned as its magic cookie. Once the procedure described above has been concluded, the cookie is set to the contents of the `$HOME/erlang.cookie` file.

To communicate with another node, the magic cookie of that node must be known. The BIF `erlang:set_cookie(Node, Cookie)` sets the cookie for Node to Cookie. From then on, all messages will be accompanied by the cookie Cookie. If the cookie is not correct when messages arrive at Node, they are sent to the `auth` server at Node. The call `erlang:set_cookie(node(), CookieAtom)` will set the current cookie to `CookieAtom`. It will, however, also set the cookie of all other unknown nodes to `CookieAtom`. In the case of the default `auth` server, this is the first thing done when the system starts. The default then, is to assume that all nodes which communicate have the same cookie. In the case of a single user on a single file system, this is indeed true and no further action is required. The original cookie can also be fetched by the BIF `erlang:get_cookie()`.

If nodes which communicate do not have the same cookie, they can be set explicitly on each node with the aid of `erlang:set_cookie(Node, Cookie)`. All messages sent to the node Node will then be accompanied by the cookie Cookie. Distributed systems with multiple User IDs can be handled in this way.

Initially, the system cookie is set to a random atom, and the (assumed) cookie of all other nodes is initially set to the atom `nocookie`. Thus, the Erlang system is completely

unprotected when `erlang:set_cookie(node(), nocookie)` is run. Sometimes, this may be appropriate for systems which are not normally networked, and it can also be appropriate for maintenance purposes.

If a user wants to write a specific application with another authentication procedure than the one provided by the standard system, passwords for example, the auth server can be replaced by a user defined server. Once this user defined authentication procedure succeeds and the two nodes can exchange cookies, both nodes will use the `set_cookie/2` BIF to set the cookie of other nodes in the network so there can be communication between them.

In the standard system, the default when two nodes are connected is to immediately connect all other involved nodes as well. This way, there is always a fully connected network. If there are nodes with different cookies, this method might be inappropriate and the host OS command line option `-connect_all false` must be issued to the Erlang system. See `global(3)`.

This module uses the two BIFs `erlang:get_cookie()` which returns the magic cookie of the local node, and `erlang:set_cookie(Node, Cookie)` which sets the magic cookie of Node to Cookie. If Node is the user's node, the cookie of all other unknown nodes are also set to Cookie by this BIF.

Exports

`start()`

Starts the auth server.

`stop()`

Stops the auth server.

`open(Name)`

This function opens up the server with the name Name. If, for example, node N is run with the cookie C, it is impossible for other nodes with other cookies to communicate with node N. The call `open/1` opens the server with the registered name Name so it can be accessed by any other node, irrespective of cookie. The call must be executed on both nodes to have any effect. All messages to the server must have the form `Name ! Msg` and all replies from the server `{Name, Reply}`, or `{Name, Node, Reply}`. With this feature, it is possible to perform specific tasks on publicly announced Erlang network servers.

`is_auth(Node)`

Returns the value yes if communication with Node is authorized, no if Node does not exist or communication is not authorized.

`exists(Node)`

Returns yes if Node exists, otherwise no.

`cookie()`

Reads `cookie` from `$HOME/.erlang.cookie` and sets it. This function is used by the auth server at start-up.

`node_cookie(Node, Cookie)`

If the cookie of `Node` is known to the user as `Cookie` but the user's cookie is not known at `Node`, this function informs `Node` of the identity of the user's cookie.

`node_cookie([Node, Cookie])`

Another version of the previous function with the arguments in a list which can be given on the host OS command line.

`cookie([Cookie])`

Equivalent to `erlang:set_cookie(node(), Cookie)`, but with the argument in a list so it can be given on the host OS command line.

code (Module)

This module deals with the loading of compiled and interpreted code into a running Erlang system.

The code server dynamically loads modules into the system on demand, which means the first time the module is referenced. This functionality can be turned off using the command line flag `-mode embedded`. In this mode, all code is loaded during system start-up.

If started in `interactive` mode, all directories under the `$ROOT/lib` directory are initially added to the search path of the code server `()`. The `$ROOT` directory is the installation directory of the Erlang system, `code:root_dir()`. Directories can be named `Name[-Vsn]` and the code server, by default, chooses the greatest (`>`) directory among those which have the same `Name`. The `-Vsn` suffix is optional.

If an `ebin` directory exists under a chosen directory, it is added to the directory. The `Name` of the directory (or library) can be used to find the full directory name (including the current version) through the `priv_dir/1` and `lib_dir/1` functions.

Exports

```
start() -> {ok, Pid} | {error, What}
start(Flags) -> {ok, Pid} | {error, What}
```

Types:

- `Flags` = `[stick | nostick | embedded | interactive]`
- `Pid` = `pid()`
- `What` = `term()`

This function starts the code server. `start/0` implies that the `stick` and `interactive` flags are set.

`Flags` can also be entered as the command line flags `-stick`, `-nostick` and `-mode embedded | interactive`. `-stick` and `-mode interactive` are the defaults. The `stick` flag indicates that a module can never be re-loaded once it has been loaded from the `kernel`, `stdlib`, or `compiler` directories.

```
start_link() -> {ok, Pid} | {error, What}
start_link(Flags) -> {ok, Pid} | {error, What}
```

Types:

- `Flags` = `[stick | nostick | embedded | interactive]`
- `Pid` = `pid()`
- `What` = `term()`

This function starts the code server and sets up a link to the calling process. This function should be used if the code server is supervised. `start_link/0` implies that the `stick` and `interactive` flags are set.

The Flags can also be given as command line flags, `-stick`, `-nostick` and `-mode embedded | interactive` where `-stick` and `-mode interactive` is the default. The `stick` flag indicates that a module which has been loaded from the kernel, `stdlib` or `compiler` directories can never be reloaded.

```
set_path(DirList) -> true | {error, What}
```

Types:

- `DirList` = `[Dir]`
- `Dir` = `string()`
- `What` = `bad_directory` | `bad_path`

Sets the code server search path to the list of directories `DirList`.

```
get_path() -> Path
```

Types:

- `Path` = `[Dir]`
- `Dir` = `string()`

Returns the current path.

```
add_path(Dir) -> true | {error, What}
```

```
add_pathz(Dir) -> true | {error, What}
```

Types:

- `Dir` = `string()`
- `What` = `bad_directory`

Adds `Dir` to the current path. The directory is added as the last directory in the new path. If `Dir` already exists in the path, it is not added.

```
add_patha(Dir) -> true | {error, What}
```

Types:

- `Dir` = `string()`
- `What` = `bad_directory`

This function adds `Dir` to the beginning of the current path. If `Dir` already exists, the old directory is removed from path.

```
add_paths(DirList) -> ok
```

```
add_pathsz(DirList) -> ok
```

Types:

- `DirList` = `[Dir]`
- `Dir` = `string()`

This function adds the directories in `DirList` to the end of the current path. If a `Dir` already exists in the path, it is not added. This function always returns `ok`, regardless of the validity of each individual `Dir`.

```
add_pathsa(DirList) -> ok
```

Types:

- `DirList` = `[Dir]`
- `Dir` = `string()`

Adds the directories in `DirList` to the beginning of the current path. If a `Dir` already exists, the old directory is removed from the path. This function always returns `ok`, regardless of the validity of each individual `Dir`.

```
del_path(NameDir) -> true | false | {error, What}
```

Types:

- `NameDir` = `Name` | `Dir`
- `Name` = `atom()`
- `Dir` = `string()`
- `What` = `bad_name`

This function deletes an old occurrence of a directory in the current path with the name `.../Name[-*] [/ebin]`. It is also possible to give the complete directory name `Dir` in order to delete it.

This function returns `true` if the directory was deleted, and `false` if the directory was not found.

```
replace_path(Name, Dir) -> true | {error, What}
```

Types:

- `Name` = `atom()`
- `Dir` = `string()`
- `What` = `bad_name` | `bad_directory` | `{badarg, term()}`

This function replaces an old occurrence of a directory named `.../Name[-*] [/ebin]`, in the current path, with `Dir`. If `Name` does not exist, it adds the new directory `Dir` last in path. The new directory must also be named `.../Name[-*] [/ebin]`. This function should be used if a new version of the directory (library) is added to a running system.

```
load_file(Module) -> {module, Module} | {error, What}
```

Types:

- `Module` = `atom()`
- `What` = `nofile` | `sticky_directory` | `badarg` | `term()`

This function tries to load the Erlang module `Module`, using the current path. It looks for the object code file which has a suffix that corresponds to the Erlang machine used, for example `Module.beam`. The loading fails if the module name found in the object code differs from the name `Module`. `load_binary/3` must be used to load object code with a module name that is different from the file name.

```
load_abs(File) -> {module, Module} | {error, What}
```

Types:

- File = atom() | string()
- Module = atom()
- What = nofile | sticky_directory | badarg | term()

This function does the same as `load_file(Module)`, but `File` is either an absolute file name, or a relative file name. The current path is not searched. It returns a value in the same way as `load_file(Module)`. Note that `File` should not contain an extension (".`.beam`"); `load_abs/1` adds the correct extension itself.

```
ensure_loaded(Module) -> {module, Module} | {error, What} | {interpret, Module}
```

Types:

- Module = atom()
- What = nofile | sticky_directory | embedded | badarg | term()

This function tries to ensure that the module `Module` is loaded. To work correctly, a file with the same name as `Module.Suffix` must exist in the current search path. `Suffix` must correspond to the running Erlang machine, for example `.beam`. It returns a value in the same way as `load_file(File)`, or `{interpret, Module}` if `Module` is interpreted.

If the system is started with the `-mode embedded` command line flag, this function will not load a module which has not already been loaded. `{error, embedded}` is returned.

```
delete(Module) -> true | false
```

Types:

- Module = atom()

This function deletes the code in `Module` and the code in `Module` is marked as old. This means that no external function calls can be made to this occurrence of `Module`, but a process which executes code inside this module continues to do so. Returns `true` if the operation was successful (i.e., there was a current version of the module, but no old version), otherwise `false`.

```
purge(Module) -> true | false
```

Types:

- Module = atom()

This function purges the code in `Module`, that is, it removes code marked as old. If some processes still execute code in the old occurrence of `Module`, these processes are killed before the module is purged. Returns `true` if a process has been killed, otherwise `false`.

```
soft_purge(Module) -> true | false
```

Types:

- Module = atom()

This function purges the code in `Module`, that is, it removes code marked as old, but only if no process currently runs the old code. It returns `false` if a process uses the old code, otherwise `true`.

```
is_loaded(Module) -> {file, Loaded} | false
```

Types:

- Module = atom()
- Loaded = AbsFileName | preloaded | interpreted
- AbsFileName = string()

This function tests if module `Module` is loaded. If the module is loaded, the absolute file name of the file from which the code was obtained is returned.

```
all_loaded() -> [LoadMod]
```

Types:

- LoadMod = {Module, Loaded}
- Module = atom()
- Loaded = AbsFileName | preloaded | interpreted
- AbsFileName = string()

This function returns a list of tuples of the type {Module, Loaded} for all loaded modules. `Loaded` is the absolute file name of the loaded module, the atom `preloaded` if the module was pre-loaded, or the atom `interpreted` if the module is interpreted.

```
load_binary(Module, File, Binary) -> {module, Module} | {error, What}
```

Types:

- Module = atom()
- What = sticky_directory | badarg | term()

This function can be used to load object code on remote Erlang nodes. It can also be used to load object code where the file name and module name differ. This, however, is a very unusual situation and should be used with care. The parameter `Binary` must contain object code for the module `Module`. The `File` parameter is only used by the code server to keep a record from which file the object code in `Module` comes.

Accordingly, `File` is not opened and read by the code server.

```
stop() -> stopped
```

Stops the code server.

```
root_dir() -> RootDir
```

Types:

- RootDir = string()

Returns the root directory of the Erlang system, which is the directory where the Erlang system is installed.

```
lib_dir() -> LibDir
```

Types:

- LibDir = string()

Returns the library directory.

```
lib_dir(Name) -> LibDir | {error, What}
```

Types:

- Name = atom()

- LibDir = string()
- What = bad_name

This function returns the current `lib` directory for the `Name[-*]` directory (or library). The current path is searched for a directory named `.../Name-*` (the `-*` suffix is optional for directories in the search path and it represents the version of the directory).

```
compiler_dir() -> CompDir
```

Types:

- CompDir = string()

This function returns the compiler directory.

```
priv_dir(Name) -> PrivDir | {error, What}
```

Types:

- Name = atom()
- PrivDir = string()
- What = bad_name

This function returns the current `priv` directory for the `Name[-*]` directory. The current path is searched for a directory named `.../Name-*` (the `-*` suffix is optional for directories in the search path and it represents the version of the directory). The `/priv` suffix is added to the end of the found directory.

```
get_object_code(Module) -> {Module, Bin, AbsFileName} | error
```

Types:

- Module = atom()
- Bin = binary()
- AbsFileName = string()

This function searches the code path in the code server for the object code of the module `Module`. It returns `{Mod, Bin, Filename}` if successful, and `error` if not. `Bin` is a binary data object which contains the object code for the module. This can be useful if code is to be loaded on a remote node in a distributed system. For example, loading module `Module` on node `N` is done as follows:

```
...
{Mod, B, F} = code:get_object_code(Mod),
rpc:call(N,code, load_binary, [Mod, F, B]),
...
```

```
objfile_extension() -> Ext
```

Types:

- Ext = string()

This function returns the object code file extension for the running Erlang machine, for example “`.beam`”.

```
stick_dir(Dir) -> ok | {error, term()}
```

Types:

- Dir = string()

This function marks `Dir` as 'sticky'. The system issues a warning and rejects the request if a user tries to re-load a module in a sticky directory. Sticky directories are used to warn the user about inadvertent changes to system software.

```
unstick_dir(Dir) -> ok | {error, term()}
```

Types:

- Dir = string()

This function unsticks a directory which has been marked sticky. Code which is located in the unstuck directory can be re-loaded into the system.

```
which(Module) -> WhichFile
```

Types:

- Module = atom()
- WhichFile = FileName | non_existing | preloaded | interpreted
- FileName = string()

If the module is not loaded already, this function returns the directory path to the first file name in the search path of the code server which contains the object code for `Module`. If the module is loaded, it returns the directory path to the file name which contains the loaded object code. If the module is pre-loaded or interpreted, this is returned instead. `non_existing` is returned if the module cannot be found.

```
clash() -> ok
```

Searches the entire code space for module names with identical names and writes a report to `stdout`.

```
interpret(Module) -> {module, Module} | {error, What}
```

Types:

- Module = atom()
- What = no_interpreter | sticky_directory | badarg

Marks `Module` as being interpreted.

```
interpret_binary(Module, File, Binary) -> {module, Module} | {error, What}
```

Types:

- Module = atom()
- File = string()
- Binary = binary()
- What = no_interpreter | sticky_directory | badarg | term()

Loads the interpreted `Module` into the interpreter. The parameter `Binary` contains the abstract form (and the source code) of the module. The file `File` parameter locates the used source code file.

```
delete_interpret(Module) -> ok | {error, What}
```

Types:

- Module = atom()
 - What = no_interpreter | badarg
- Stops interpretation of Module.

`interpreted() -> Modules`

Types:

- Modules = [Module]
- Module = atom()

Returns a list of all modules which are being interpreted.

`interpreted(Module) -> true | false`

Types:

- Module = atom()

Returns true if Module is being interpreted, otherwise false.

Notes

Dir has the described type `string()` in all functions. For backwards compatibility, `atom()` is also allowed, but `string()` is recommended.

The described type for Module is `atom()` in all functions. For backwards compatibility, `string()` is also allowed.

disk_log (Module)

`disk_log` is a disk based term logger which makes it possible to efficiently log items on files. Two types of logs are supported, *halt logs* and *wrap logs*. A halt log appends items to a single file, the size of which may or may not be limited by the disk log module, whereas a wrap log utilizes a sequence of wrap log files of limited size. As a wrap log file has been filled up, further items are logged onto to the next file in the sequence, starting all over with the first file when the last file has been filled up. For the sake of efficiency, items are always written to files as binaries.

Two formats of the log files are supported, the *internal format* and the *external format*. The internal format supports automatic repair of log files that have not been properly closed, and makes it possible to efficiently read logged items in *chunks* using a set of functions defined in this module. In fact, this is the only way to read internally formatted logs. The external format leaves it up to the user to read the logged deep byte lists. The disk log module cannot repair externally formatted logs.

For each open disk log there is one process that handles requests made to the disk log; the disk log process is created when `open/1` is called, provided there exists no process handling the disk log. A process that opens a disk log can either be an *owner* or an anonymous *user* of the disk log. An owner is linked to the disk log process, and the disk log is closed by the owner should the owner terminate. Owners can subscribe to *notifications*, messages of the form `{disk_log, Node, Log, Info}` that are sent from the disk log process when certain events occur, see the commands below and in particular the `open/1` option `notify`. There can be several owners of a log, but a process cannot own a log more than once. One and the same process may, however, open the log as a user more than once. For a disk log process to properly close its file and terminate, it must be closed by its owners and once by some non-owner process for each time the log was used anonymously; the users are counted, and there must not be any users left when the disk log process terminates.

Items can be logged *synchronously* by using the functions `log/2`, `blog/2`, `log_terms/2` and `blog_terms/2`. For each of these functions, the caller is put on hold until the items have been logged (but not necessarily written, use `sync/1` to ensure that). By adding an `a` to each of the mentioned function names we get functions that log items *asynchronously*. Asynchronous functions do not wait for the disk log process to actually write the items to the file, but return the control to the caller more or less immediately.

When using the internal format for logs, the functions `log/2`, `log_terms/2`, `alog/2`, and `alog_terms/2` should be used. These functions log one or more Erlang terms. By prefixing each of the functions with a `b` (for “binary”) we get the corresponding `blog` functions for the external format. These functions log one or more deep lists of bytes or, alternatively, binaries of deep lists of bytes. For example, to log the string “hello” in ASCII format, we can use `disk_log:blog(Log, "hello")`, or `disk_log:blog(Log, list_to_binary("hello"))`. The two alternatives are equally efficient. The `blog` functions can be used for internally formatted logs as well, but in this case they must be called with binaries constructed with calls to `term_to_binary/1`. There is no check to ensure this, it is entirely the responsibility of the caller. If these functions are called with binaries that do not correspond to Erlang terms, the `chunk/2,3` and automatic repair

functions will fail. The corresponding terms (not the binaries) will be returned when `chunk/2,3` is called.

Disk logs can be configured to log to files on several nodes in parallel. When *distributed* this way, the log is globally accessible. It is not guaranteed that all log files contain the same log items. This functionality ensures that as long as at least one of the involved nodes is alive at each time, all log items will be logged. If all nodes are down, the disk log functions reply with a `nonode` error.

Errors are reported differently for asynchronous log attempts and other uses of the disk log module. When used synchronously the disk log module replies with an error message, but when called asynchronously, the disk log module does not know where to send the error message. Instead owners subscribing to notifications will receive an `error_status` message.

The disk log module itself does not report errors to the `error_logger` module; it is up to the caller to decide whether the error logger should be employed or not. The function `format_error/1` can be used to produce readable messages from error replies.

Exports

```
alog(Log, Term) -> ok | {error, Reason}
balog(Log, Bytes) -> ok | {error, Reason}
```

Types:

- `Log` = `term()`
- `Term` = `term()`
- `Bytes` = `binary()` | `[Byte]`
- `Byte` = `[Byte]` | `0 = < integer() = < 255`
- `Reason` = `no_such_log`

The `alog/2` and `balog/2` functions asynchronously append an item to a disk log. The function `alog/2` is used for internally formatted logs, and the function `balog/2` for externally formatted logs. `balog/2` can be used for internally formatted logs as well provided the binary was constructed with a call to `term_to_binary/1`.

The owners that subscribe to notifications will receive the message `read_only`, `blocked_log` or `format_external` in case the item cannot be written on the log, and possibly one of the messages `wrap`, `full` and `error_status` if an item was written on the log. The message `error_status` is sent if there is something wrong with the header function or a file error occurred.

```
alog_terms(Log, TermList) -> ok | {error, Reason}
balog_terms(Log, BytesList) -> ok | {error, Reason}
```

Types:

- `Log` = `term()`
- `TermList` = `[term()]`
- `BytesList` = `[Bytes]`
- `Bytes` = `binary()` | `[Byte]`
- `Byte` = `[Byte]` | `0 = < integer() = < 255`

- Reason = no_such_log

The alog_terms/2 and balog_terms/2 functions asynchronously append a list of items to a disk log. The function alog_terms/2 is used for internally formatted logs, and the function balog_terms/2 for externally formatted logs. balog_terms/2 can be used for internally formatted logs as well provided the binaries were constructed with calls to term_to_binary/1.

The owners that subscribe to notifications will receive the message read_only, blocked_log or format_external in case the items cannot be written on the log, and possibly one or more of the messages wrap, full and error_status if items were written on the log. The message error_status is sent if there is something wrong with the header function or a file error occurred.

```
block(Log)
block(Log, QueueLogRecords) -> ok | {error, Reason}
```

Types:

- Log = term()
- QueueLogRecords = bool()
- Reason = no_such_log | nonode | {blocked_log, Log}

With a call to block/1,2 a process can block a log. If the blocking process is not an owner of the log, a temporary link is created between the disk log process and the blocking process. The link is used to ensure that the disk log is unblocked should the blocking process terminate without first closing or unblocking the log.

Any process can probe a blocked log with info/1 or close it with close/1. The blocking process can also use the functions chunk/2,3, chunk_step/3, and unblock/1 without being affected by the block. Any other attempt than those hitherto mentioned to update or read a blocked log suspends the calling process until the log is unblocked or returns an error message {blocked_log, Log}, depending on whether the value of QueueLogRecords is true or false. The default value of QueueLogRecords is true, which is used by block/1.

```
change_header(Log, Header) -> ok | {error, Reason}
```

Types:

- Log = term()
- Header = {head, Head} | {head_func, {M,F,A}}
- Head = none | term() | binary() | [Byte]
- Byte = [Byte] | 0 <= integer() <= 255
- Reason = no_such_log | nonode | {read_only_mode, Log} | {blocked_log, Log} | {badarg, head}

The change_header/2 function changes the value of the head or head_func option of a disk log.

```
change_notify(Log, Owner, Notify) -> ok | {error, Reason}
```

Types:

- Log = term()
- Owner = pid()
- Notify = bool()

- Reason = no_such_log | nonode | {blocked_log, Log} | {badarg, notify} | {not_owner, Owner}

The `change_notify/3` function changes the value of the `notify` option for an owner of a disk log.

```
change_size(Log, Size) -> ok | {error, Reason}
```

Types:

- Log = term()
- Size = integer() > 0 | infinity | {MaxNoBytes, MaxNoFiles}
- MaxNoBytes = integer() > 0
- MaxNoFiles = integer() > 0
- Reason = no_such_log | nonode | {read_only_mode, Log} | {blocked_log, Log} | {new_size_too_small, CurrentSize} | {badarg, size} | {file_error, FileName, FileError}

The `change_size/2` function changes the size of an open log. For a halt log it is always possible to increase the size, but it is not possible to decrease the size to something less than the current size of the file.

For a wrap log it is always possible to increase both the size and number of files, as long as the number of files does not exceed 65000. If the maximum number of files is decreased, the change will not be valid until the current file is full and the log wraps to the next file. The redundant files will be removed next time the log wraps around, i.e. starts to log to file number 1.

As an example, assume that the old maximum number of files is 10 and that the new maximum number of files is 6. If the current file number is not greater than the new maximum number of files, the files 7 to 10 will be removed when file number 6 is full and the log starts to write to file number 1 again. Otherwise the files greater than the current file will be removed when the current file is full (e.g. if the current file is 8, the files 9 and 10); the files between new maximum number of files and the current file (i.e. files 7 and 8) will be removed next time file number 6 is full.

If the size of the files is decreased the change will immediately affect the current log. It will not of course change the size of log files already full until next time they are used.

If the log size is decreased for instance to save space, the function `inc_wrap_file/1` can be used to force the log to wrap.

```
chunk(Log, Continuation)
chunk(Log, Continuation, N) -> {Continuation2, Terms} | {Continuation2, Terms,
    Badbytes} | eof | {error, Reason}
```

Types:

- Log = term()
- Continuation = start | cont()
- N = integer() > 0 | infinity
- Continuation2 = cont()
- Terms= [term()]
- Badbytes = integer()
- Reason = no_such_log | {format_external, Log} | {blocked_log, Log} | {not_internal_wrap, Log} | {corrupt_log_file, FileName} | {file_error, FileName, FileError}

The `chunk/2,3` functions make it possible to efficiently read the terms which have been appended to an internally formatted log. It minimizes disk I/O by reading 8 kilobyte chunks from the file.

The first time `chunk` is called, an initial continuation, the atom `start`, must be provided.

When `chunk/3` is called, `N` controls the maximum number of terms that are read from the log in each chunk. Default is `infinity`, which means that all the terms contained in the 8 kilobyte chunk are read. If less than `N` terms are returned, this does not necessarily mean that the end of the file has been reached.

The `chunk` function returns a tuple `{Continuation2, Terms}`, where `Terms` is a list of terms found in the log. `Continuation2` is yet another continuation which must be passed on into any subsequent calls to `chunk`. With a series of calls to `chunk` it is possible to extract all terms from a log.

The `chunk` function returns a tuple `{Continuation2, Terms, Badbytes}` if the log is opened in read-only mode and the read chunk is corrupt. `Badbytes` is the number of bytes in the file which were found not to be Erlang terms in the chunk. Note also that the log is not repaired. When trying to read chunks from a log opened in read-write mode, the tuple `{corrupt_log_file, FileName}` is returned if the read chunk is corrupt.

`chunk` returns `eof` when the end of the log is reached, or `{error, Reason}` if an error occurs. Should a wrap log file be missing, a message is output on the error log.

When `chunk/2,3` is used with wrap logs, the returned continuation may or may not be valid in the next call to `chunk`. This is because the log may wrap and delete the file into which the continuation points. To make sure this does not happen, the log can be blocked during the search.

```
chunk_step(Log, Continuation, Step) -> {ok, Continuation2} | {error, Reason}
```

Types:

- `Log = term()`
- `Continuation = start | cont()`
- `Step = integer()`
- `Continuation2 = cont()`
- `Reason = no_such_log | end_of_log | {format_external, Log} | {blocked_log, Log} | {file_error, FileName, FileError}`

The function `chunk_step` can be used in conjunction with `chunk/2,3` to search through an internally formatted wrap log. It takes as argument a continuation as returned by `chunk/2,3` or `chunk_step/3`, and steps forward (or backward) `Step` files in the wrap log. The continuation returned points to the first log item in the new current file.

If the wrap log is not full because all files have not been used yet, `{error, end_of_log}` is returned if trying to step outside the log.

```
close(Log) -> ok | {error, Reason}
```

Types:

- `Reason = no_such_log | nonode`

The function `close/1` closes a log file properly. An internally formatted log must be closed before the system is stopped, otherwise the log is regarded as unclosed and the automatic repair procedure will be activated next time the log is opened.

The disk log process is not terminated as long as there are owners or users of the log. It should be stressed that each and every owner must close the log, possibly by terminating, and that any other process - not only the processes that have opened the log anonymously - can decrement the `users` counter by closing the log. Attempts to close a log by a process that is not an owner are simply ignored if there are no users.

If the log is blocked by the closing process, the log is also unblocked.

```
format_error(Error) -> character_list()
```

Given the error returned by any function in this module, the function `format_error` returns a descriptive string of the error in English. For file errors, the function `format_error/1` in the `file` module is called.

```
inc_wrap_file(Log) -> ok | {error, Reason}
```

Types:

- `Reason = no_such_log | nonode | {read_only_mode, Log} | {blocked_log, Log} | {halt_log, Log} | {invalid_header, InvalidHeader} | {file_error, FileName, FileNotFoundError}`

The `inc_wrap_file/1` function forces the disk log to start logging to the next log file. It can be used, for instance, in conjunction with `change_size/2` in order to save disk space.

The owners that subscribe to notifications will normally receive a `wrap` message, but in case of an error with a reason tag of `invalid_header` or `file_error` an `error_status` message will be sent.

```
info(Log) -> InfoList | {error, no_such_log}
```

The `info/1` function returns a list of `{Tag, Value}` pairs describing the log. The following pairs are returned for all logs:

- `{name, Log}`, where `Log` is the name of the log as given by the `open/1` option `name`.
- `{file, File}`. For halt logs `File` is the filename, and for wrap logs `File` is the base name.
- `{type, Type}`, where `Type` is the type of the log as given by the `open/1` option `type`.
- `{format, Format}`, where `Format` is the format of the log as given by the `open/1` option `format`.
- `{size, Size}`, where `Size` is the size of the log as given by the `open/1` option `size`, or the size set by `change_size/2`. The value set by `change_size/2` is reflected immediately.
- `{mode, Mode}`, where `Mode` is the mode of the log as given by the `open/1` option `mode`.
- `{owners, [{pid(), Notify}]}` where `Notify` is the value set by the `open/1` option `notify` or the function `change_notify/3` for the owners of the log.
- `{users, Users}` where `Users` is the number of anonymous users of the log, see the `open/1` option `linkto`.
- `{status, Status}`, where `Status` is `ok` or `{blocked, QueueLogRecords}` as set by the functions `block/1,2` and `unblock/1`.

The following pairs are returned for all logs opened in `read_write` mode:

- `{head, Head}`. Depending of the value of the `open/1` options `head` and `head_func` or set by the function `change_head/2`, the value of `Head` is `none` (default), `{head, H}` (`head` option) or `{M, F, A}` (`head_func` option).
- `{no_written_items, NoWrittenItems}`, where `NoWrittenItems` is the number of items written to the log since the disk log process was created.

The following pair is returned for halt logs opened in `read_write` mode:

- `{full, Full}`, where `Full` is `true` or `false` depending on whether the halt log is full or not.

The following pairs are returned for wrap logs opened in `read_write` mode:

- `{no_current_bytes, integer() >= 0}` is the number of bytes written to the current wrap log file.
- `{no_current_items, integer() >= 0}` is the number of items written to the current wrap log file, header inclusive.
- `{no_items, integer() >= 0}` is the total number of items in all wrap log files.
- `{current_file, integer()}` is the ordinal for the current wrap log file in the range `1..MaxNoFiles`, where `MaxNoFiles` is given by the `open/1` option `size` or set by `change_size/2`.
- `{no_overflows, {SinceLogWasOpened, SinceLastInfo}}`, where `SinceLogWasOpened (SinceLastInfo)` is the number of times a wrap log file has been filled up and a new one opened or `inc_wrap_file/1` has been called since the disk log was last opened (`info/1` was last called). The first time `info/2` is called after a log was (re)opened or truncated, the two values are equal.

Note that the `chunk/2,3` and `chunk_step/3` functions do not affect any value returned by `info/1`.

```
log(Log, Term) -> ok | {error, Reason}
blog(Log, Bytes) -> ok | {error, Reason}
```

Types:

- `Log = term()`
- `Term = term()`
- `Bytes = binary() | [Byte]`
- `Byte = [Byte] | 0 =< integer() =< 255`
- `Reason = no_such_log | nonode | {read_only_mode, Log} | {format_external, Log} | {blocked_log, Log} | {full, Log} | {invalid_header, InvalidHeader} | {file_error, FileName, FileError}`

The `log/2` and `blog/2` functions synchronously append a term to a disk log. They return `ok` or `{error, Reason}` when the term has been written to disk. Terms are written by means of the ordinary `write()` function of the operating system. Hence, there is no guarantee that the term has actually been written to the disk, it might linger in the operating system kernel for a while. To make sure the item is actually written to disk, the `sync/1` function must be called.

The `log/2` function is used for internally formatted logs, and `blog/2` for externally formatted logs. `blog/2` can be used for internally formatted logs as well provided the binary was constructed with a call to `term_to_binary/1`.

The owners that subscribe to notifications will be notified of an error with an `error_status` message if the error reason tag is `invalid_header` or `file_error`.

```
log_terms(Log, TermList) -> ok | {error, Reason}
blog_terms(Log, BytesList) -> ok | {error, Reason}
```

Types:

- `Log` = `term()`
- `TermList` = `[term()]`
- `BytesList` = `[Bytes]`
- `Bytes` = `binary()` | `[Byte]`
- `Byte` = `[Byte]` | `0 = < integer() = < 255`
- `Reason` = `no_such_log` | `nonode` | `{read_only_mode, Log}` | `{format_external, Log}` | `{blocked_log, Log}` | `{full, Log}` | `{invalid_header, InvalidHeader}` | `{file_error, FileName, FileError}`

The `log_terms/2` and `blog_terms/2` functions synchronously append a list of items to the log. The benefit of using these functions rather than the `log/2` and `blog/2` functions is that of efficiency: the given list is split into as large sublists as possible (limited by the size of wrap log files), and each sublist is logged as one single item, which reduces the overhead.

The `log_terms/2` function is used for internally formatted logs, and `blog_terms/2` for externally formatted logs. `blog_terms/2` can be used for internally formatted logs as well provided the binaries were constructed with calls to `term_to_binary/1`.

The owners that subscribe to notifications will be notified of an error with an `error_status` message if the error reason tag is `invalid_header` or `file_error`.

```
open(ArgL) -> OpenRet
```

Types:

- `ArgL` = `[Opt]`
- `Opt` = `{name, term()}` | `{file, FileName}`, `{linkto, LinkTo}` | `{repair, Repair}` | `{type, Type}` | `{format, Format}` | `{size, Size}` | `{distributed, [Node]}` | `{notify, bool()}` | `{head, Head}` | `{head_func, {M,F,A}}` | `{mode, Mode}`
- `FileName` = `string()` | `atom()`
- `LinkTo` = `pid()` | `none`
- `Repair` = `true` | `false` | `truncate`
- `Type` = `halt` | `wrap`
- `Format` = `internal` | `external`
- `Size` = `integer() > 0` | `infinity` | `{MaxNoBytes, MaxNoFiles}`
- `MaxNoBytes` = `integer() > 0`
- `MaxNoFiles` = `integer() > 0`
- `Rec` = `integer()`
- `Bad` = `integer()`
- `Node` = `atom()`
- `Head` = `none` | `term()` | `binary()` | `[Byte]`

- Byte = [Byte] | 0 =< integer() =< 255
- Mode = read_write | read_only
- OpenRet = {ok, Log} | {repaired, Log, {recovered, Rec}, {badbytes, Bad}} | {error, Reason} | DistRet
- DistRet = {[{Node, OpenRet}], [{BadNode, {error, DistReason}}]}
- Reason = no_such_log | {badarg, Arg} | {size_mismatch, CurrentSize, NewSize} | {arg_mismatch, OptionName, CurrentValue, Value} | {name_already_open, Log} | {open_read_write, Log} | {open_read_only, Log} | {need_repair, Log} | {not_a_log_file, FileName} | {invalid_index_file, FileName} | {invalid_header, InvalidHeader} | {file_error, FileName, FileError}

The ArgL parameter is a list of options which have the following meanings:

- {name, Log} specifies the name of the log. This is the name which must be passed on as a parameter in all subsequent logging operations. A name must always be supplied.
- {file, FileName} specifies the name of the file which will be used for logged terms. If this value is omitted and the name of the log is either an atom or a string, the file name will default to lists:concat([Log, ".LOG"]) for halt logs. For wrap logs, this will be the base name of the files. Each file in a wrap log will be called <base_name>.N, where N is an integer. Each wrap log will also have two files called <base_name>.idx and <base_name>.siz.
- {linkto, LinkTo}. If LinkTo is a pid, that pid becomes an owner of the log. If LinkTo is none the log records that it is used anonymously by some process by incrementing the users counter. By default, the process which calls open/1 owns the log.
- {repair, Repair}. If Repair is true, the current log file will be repaired, if needed. As the restoration is initiated, a message is output on the error log. If false is given, no automatic repair will be attempted. Instead, the tuple {error, {need_repair, Log}} is returned if an attempt is made to open a corrupt log file. If truncate is given, the log file will be truncated, creating an empty log. Default is true, which has no effect on logs opened in read-only mode.
- {type, Type} is the type of the log. Default is halt.
- {format, Format} specifies the format of the disk log. Default is internal.
- {size, Size} specifies the size of the log. When a halt log reaches its maximum size, all attempts to log more items are rejected. The default size is infinity, which for halt implies that there is no maximum size. For wrap logs, the Size parameter may be either a pair {MaxNoBytes, MaxNoFiles} or infinity. In the latter case, if the files of an already existing wrap log with the same name can be found, the size is read from the existing wrap log, otherwise an error is returned. Wrap logs write at most MaxNoBytes bytes on each file and use MaxNoFiles files before starting all over with the first wrap log file. MaxNoFiles must not exceed 65000. When opening an existing log, it is not necessary to supply a value for the option Size, but any supplied value must equal the current size of the log, otherwise the tuple {error, {size_mismatch, CurrentSize, NewSize}} is returned.
- {distributed, Nodes}. This option should be used to make a log globally visible and replicated on several nodes. If the log does not exist on any node, it is created. If the log does exist on some nodes, Nodes are joined to the existing nodes. The recommended way of using this functionality is to open the log with {distributed, [node()]} on each node. The module pg2 is used to address the logs. The default value is [], which means that the log is not distributed.

- `{notify, bool()}`. If true, the owners of the log are notified when certain events occur in the log. Default is false. The owners are sent one of the following messages when an event occurs:
 - `{disk_log, Node, Log, {wrap, NoLostItems}}` is sent when a wrap log has filled up one of its files and a new file is opened. In case of using one of the functions that append a list of items to a log fills up several files, only one message is sent. `NoLostItems` is the number of previously logged items that have been lost when truncating existing files.
 - `{disk_log, Node, Log, {truncated, NoLostItems}}` is sent when a log has been truncated or reopened. For halt logs `NoLostItems` is the number of items written on the log since the disk log process was created. For wrap logs `NoLostItems` is the number of items on all wrap log files.
 - `{disk_log, Node, Log, {read_only, Items}}` is sent when an asynchronous log attempt is made to a log file opened in read-only mode. `Items` is the items from the log attempt.
 - `{disk_log, Node, Log, {blocked_log, Items}}` is sent when an asynchronous log attempt is made to a blocked log that does not queue log attempts. `Items` is the items from the log attempt.
 - `{disk_log, Node, Log, {format_external, Items}}` is sent when `alog/2` or `alog_terms/2` is used for internally formatted logs. `Items` is the items from the log attempt.
 - `{disk_log, Node, Log, full}` is sent when an attempt to log items to a wrap log would write more bytes than the limit set by the `size` option.
 - `{disk_log, Node, Log, {error_status, Status}}` is sent when the error status changes. The error status is defined by the outcome of the last attempt to log items to a the log or to truncate the log or the last use of `sync/1`, `inc_wrap_file/1` or `change_size/2`. `Status` is one of `ok` and `{error, Error}`, the former being the initial value.
- `{head, Head}` specifies a header to be written first on the log file. If the log is a wrap log, the item `Head` is written first in each new file. `Head` should be a term if the format is `internal`, and a deep list of bytes (or a binary) otherwise. Default is `none`, which means that no header is written first on the file.
- `{head_func, {M,F,A}}` specifies a function to be called each time a new log file is opened. The call `M:F(A)` is assumed to return `{ok, Head}`. The item `Head` is written first in each file. `Head` should be a term if the format is `internal`, and a deep list of bytes (or a binary) otherwise.
- `{mode, Mode}` specifies if the log is to be opened in read-only or read-write mode. It defaults to `read_write`.

The `open/1` function returns `{ok, Log}` if the log file was successfully opened. If the file was successfully repaired, the tuple `{repaired, Log, {recovered, Rec}, {badbytes, Bad}}` is returned, where `Rec` is the number of whole Erlang terms found in the file and `Bad` is the number of bytes in the file which were non-Erlang terms. If the distributed parameter was given, `open/1` returns a list of successful replies and a list of erroneous replies. Each reply is tagged with the node name.

When a disk log is opened in read-write mode, any existing log file is checked for. If there is none a new empty log is created, otherwise the existing file is opened at the position after the last logged item, and the logging of items will commence from there. If the format is `internal` and the existing file is not recognized as an internally formatted log, a tuple `{error, {not_a_log_file, FileName}}` is returned.

The open/1 function ensures that the log server is started. Accordingly, it is not necessary to explicitly start the server first.

The open/1 function cannot be used for changing the values of options of an already open log; when there are prior owners or users of a log, all option values except name, linkto and notify are just checked against the values that have been supplied before as option values to open/1, change_head/2, change_notify/3 or change_size/2. As a consequence, none of the options except name is mandatory. If some given value differs from the current value, a tuple {error, {arg_mismatch, OptionName, CurrentValue, Value}} is returned. Caution: An owner's attempt to open a log as owner once again is acknowledged with the return value {ok, Log}, but the state of the disk log is not affected in any way.

It is possible to open a log file more than once by giving different values to the option name. It is up to the user of the disk_log module to ensure that no more than one disk log process has write access to any file.

If an attempt to open a log file for the first time fails, the disk log process terminates with the EXIT message {{failed,Reason}, [{disk_log,open,1}]} . The function returns {error, Reason} for all other errors.

```
reopen(Log, File)
reopen(Log, File, Head)
breopen(Log, File, BHead) -> ok | {error, Reason}
```

Types:

- Log = term()
- File = string()
- Head = term()
- BHead = binary() | [Byte]
- Byte = [Byte] | 0 =< integer() =< 255
- Reason = no_such_log | nonode | {read_only_mode, Log} | {blocked_log, Log} | {same_file_name, Log} | {invalid_index_file, FileName} | {invalid_header, InvalidHeader} | {file_error, FileName, FileError}

The reopen functions first rename the log file to File and then re-create a new log file. In case of a wrap log, File is used as the base name of the renamed files. By default the header given to open/1 is written first in the newly opened log file, but if the Head or the BHead argument is given, this item is used instead. The header argument is used once only; next time a wrap log file is opened, the header given to open/1 is used.

The reopen/2,3 functions are used for internally formatted logs, and breopen/3 for externally formatted logs.

The owners that subscribe to notifications will receive a truncate message.

Upon failure to reopen the log, the disk log process terminates with the EXIT message {{failed,Error}, [{disk_log,Fun,Arity}]}, and other processes that have requests queued receive the message {disk_log, Node, {error, disk_log_stopped}}.

```
sync(Log) -> ok | {error, Reason}
```

Types:

- Log = term()
- Reason = no_such_log | nonode | {read_only_mode, Log} | {blocked_log, Log} | {file_error, FileName, FileError}

The `sync/1` function ensures that the contents of the log is actually written to the disk. This is usually a rather expensive operation.

```
truncate(Log)
truncate(Log, Head)
btruncate(Log, BHead) -> ok | {error, Reason}
```

Types:

- `Log` = `term()`
- `Head` = `term()`
- `BHead` = `binary()` | `[Byte]`
- `Byte` = `[Byte]` | `0 = < integer() = < 255`
- `Reason` = `no_such_log` | `nonode` | `{read_only_mode, Log}` | `{blocked_log, Log}` | `{invalid_header, InvalidHeader}` | `{file_error, FileName, FileError}`

The `truncate` functions remove all items from a disk log. If the `Head` or the `BHead` argument is given, this item is written first in the newly truncated log, otherwise the header given to `open/1` is used. The header argument is only used once; next time a wrap log file is opened, the header given to `open/1` is used.

The `truncate/1,2` functions are used for internally formatted logs, and `btruncate/2` for externally formatted logs.

The owners that subscribe to notifications will receive a `truncate` message.

If the attempt to truncate the log fails, the disk log process terminates with the `EXIT` message `{failed,Reason}, [{disk_log,Fun,Arity}]`, and other processes that have requests queued receive the message `{disk_log, Node, {error, disk_log_stopped}}`.

```
unblock(Log) -> ok | {error, Reason}
```

Types:

- `Log` = `term()`
- `Reason` = `no_such_log` | `nonode` | `{not_blocked, Log}` | `{not_blocked_by_pid, Log}`

The `unblock/1` function unblocks a log. A log can only be unblocked by the blocking process.

See Also

`file(3)`, `pg2(3)`, `wrap_log_reader(3)`

erl_boot_server (Module)

This server is used to assist diskless Erlang systems which fetch all Erlang code from another machine.

This server is used to fetch all code, including the start script, if an Erlang system is started with the `-loader inet` command line flag. All hosts specified with the `-hosts` Host flag must have one instance of this server running.

This server can be started with the kernel configuration parameter `start_boot_server`.

Exports

`start(Slaves) -> {ok, Pid} | {error, What}`

Types:

- `Slaves = [Host]`
- `Host = atom()`
- `Pid = pid()`
- `What = void()`

Starts the boot server. `Slaves` is a list of IP addresses for hosts which are allowed to use this server as a boot server.

`start_link(Slaves) -> {ok, Pid} | {error, What}`

Types:

- `Slaves = [Host]`
- `Host = atom()`
- `Pid = pid()`
- `What = void()`

Starts the boot server and links to the caller. This function is used to start the server if it is included in a supervision tree.

`add_slave(Slave) -> ok | {error, What}`

Types:

- `Slave = Host`
- `Host = atom()`
- `What = void()`

Adds a `Slave` node to the list of allowed slave hosts.

```
delete_slave(Slave) -> ok | {error, What}
```

Types:

- Slave = Host
- Host = atom()
- What = void()

Deletes a Slave node from the list of allowed slave hosts.

```
which_slaves() -> Slaves
```

Types:

- Slaves = [Host]
- Host = atom()

Returns the current list of allowed slave hosts.

SEE ALSO

[init\(3\)](#), [erl_prim_loader\(3\)](#)

erl_ddll (Module)

The `erl_ddll` module can load and link a linked-in driver, if run-time loading and linking of shared objects, or dynamic libraries, is supported by the underlying operating system.

Exports

`start() -> {ok, Pid} | {error, Reason}`

Starts `ddll_server`. The error return values are the same as for `gen_server`.

`start_link() -> {ok, Pid} | {error, Reason}`

Starts `ddll_server` and links it to the calling process. The error return values are the same as for `gen_server`.

`stop() -> ok`

Stops `ddll_server`.

`load_driver(Path, Name) -> ok | {error, ErrorDescriptor}`

Types:

- `Name = string() | atom()`
- `Path = string() | atom()`

Loads and links the dynamic driver `Name`. `Name` must be sharable object/dynamic library. Two drivers with different `Paths` cannot be loaded under the same name. The number of dynamically loadable drivers are limited by the size of `driver_tab` in `config.c`.

If the server is not started the caller will crash.

`unload_driver(Name) -> ok | {error, ErrorDescriptor}`

Types:

- `Name = string() | atom()`

Unloads the dynamic driver `Name`. This will fail if any port programs are running the code that is being unloaded. Linked-in driver cannot be unloaded. The process must previously have called `load_driver/1` for the driver.

There is no guarantee that the memory where the driver was loaded is freed. This depends on the underlying operating system.

If the server is not started the caller will crash.

```
loaded_drivers() -> {ok, DriverList}
```

Types:

- DriverList = [Driver()]
- Driver = string()

Returns a list of all the available drivers, both (statically) linked-in and dynamically loaded ones.

If the server is not started the caller will crash.

```
format_error(ErrorDescriptor) -> string()
```

Takes an ErrorDescriptor which has been returned by one of `load_driver/2` and `unload_driver/1` and returns a string which describes the error or warning.

Differences Between Statically Linked-in Drivers and Dynamically Loaded Drivers

Except for the following minor changes, all information in Appendix E of Concurrent Programming in Erlang, second edition, still applies.

The `driver_entry` struct has two new members: `finish` and `handle`.

Before the driver is unloaded, the `finish` function is called, without arguments, to give the driver writer a chance to clean up and release memory allocated in `driver_init`.

The member `handle` contains a pointer obtained from the operating system when the driver was loaded. Without this, the driver cannot be unloaded!

The `init` function in struct `driver_entry` is not used anymore. After the driver is loaded, the function `struct driver_entry *driver_init(void *)` is called with `handle` as argument. If the operating system loader cannot find a function called `driver_init`, the driver will not be loaded. The `driver_init` function *must* initialize a struct `driver_entry` and return a pointer to it.

Example:

```
#include <stdio.h>
#include "driver.h"
static long my_start();
static int my_stop(), my_read();
static struct driver_entry my_driver_entry;
/*
 * Initialize and return a driver entry struct
 */
struct driver_entry *driver_init(void *handle)
{
    my_driver_entry.init = null_func;      /* Not used */
    my_driver_entry.start = my_start;
    my_driver_entry.stop = my_stop;
    my_driver_entry.output = my_read;
    my_driver_entry.ready_input = null_func;
    my_driver_entry.ready_output = null_func;
    my_driver_entry.driver_name = "my_driver";
```

```
my_driver_entry.finish = null_func;
my_driver_entry.handle = handle; /* MUST set this!!! */
return &my_driver_entry;
}
```

config.c

The size of the `driver_tab` array, defined in `config.c`, limits the number of dynamically loadable drivers.

Compiling Your Driver

Please refer to your C compiler or operating system documentation for information about producing a sharable object or DLL.

The include file `driver.h` is found in the `usr/include` directory of the Erlang installation.

erl_prim_loader (Module)

The `erl_prim_loader` is used to load all Erlang modules into the system. The start script is also fetched with the low level loader.

The `erl_prim_loader` knows about the environment and how to fetch modules. The loader could, for example, fetch files using the file system (with absolute file names as input), or a database (where the binary format of a module is stored).

The `-loader Loader` command line flag can be used to choose the method used by the `erl_prim_loader`. Two Loader methods are supported by the Erlang system: `efile` and `inet`. If another loader is required, then it has to be implemented by the user. The Loader provided by the user must fulfill the protocol defined below, and it is started with the `erl_prim_loader` by evaluating `open_port({spawn,Loader}, [binary])`.

Exports

```
start(Id,Loader,Hosts) -> {ok, Pid} | {error, What}
```

Types:

- `Id` = `term()`
- `Loader` = `atom()`
- `Hosts` = `[Host]`
- `Host` = `atom()`
- `Pid` = `pid()`
- `What` = `term()`

Starts the Erlang low level loader. This function is called by the init process (and module). The init process reads the command line flags `-id Id`, `-loader Loader`, and `-hosts Hosts`. These are the arguments supplied to the `start/3` function.

If `-loader` is not given, the default loader is `efile` which tells the system to read from the file system.

If `-loader` is `inet`, the `-id Id`, `-hosts Hosts`, and `-setcookie Cookie` flags must also be supplied. `Hosts` identifies hosts which this node can contact in order to load modules. One Erlang system with a `erl_boot_server` process must be started on each of hosts given in `Hosts` in order to answer the requests. See `erl_boot_server(3)`.

If `-loader` is something else, the given port program is started. The port program is supposed to follow the protocol specified below.

```
get_file(File) -> {ok, Bin, FullName} | error
```

Types:

- `File` = `string()`

- Bin = binary()
- FullName = string()

This function fetches a file using the low level loader. `File` is either an absolute file name or just the name of the file, for example "lists.beam". If an internal path is set to the loader, this path is used to find the file. If a user supplied loader is used, the path can be stripped off if it is obsolete, and the loader does not use a path. `FullName` is the complete name of the fetched file. `Bin` is the contents of the file as a binary.

```
get_path() -> {ok, Path}
```

Types:

- Path = [Dir]
- Dir = string()

This function gets the path set in the loader. The path is set by the `init` process according to information found in the start script.

```
set_path(Path) -> ok
```

Types:

- Path = [Dir]
- Dir = string()

This function sets the path of the loader if `init` interprets a `path` command in the start script.

Protocol

The following protocol must be followed if a user provided loader port program is used. The Loader port program is started with the command `open_port({spawn,Loader},[binary])`. The protocol is as follows:

Function	Send	Receive
<hr/>		
get_file	[102 FileName]	[121 BinaryFile] (on success) [122] (failure)
stop	eof	terminate

Command Line Flags

The `erl_prim_loader` module interprets the following flags:

- `-loader Loader`** Specifies the name of the loader used by `erl_prim_loader`. Loader can be `efile` (use the local file system), or `inet` (load using the `boot_server` on another Erlang node). If Loader is user defined, the defined Loader port program is started.
If the `-loader` flag is omitted, it defaults to `efile`.
- `-hosts Hosts`** Specifies which other Erlang nodes the `inet` loader can use. This flag is mandatory if the `-loader inet` flag is present. On each host, there must be one Erlang node with the `erl_boot_server` which handles the load requests. Hosts is a list of IP addresses (hostnames are not acceptable).
- `-id Id`** Specifies the identity of the Erlang system. If the system runs as a distributed node, Id must be identical to the name supplied with the `-sname` or `-name` distribution flags.
- `-setcookie Cookie`** Specifies the cookie of the Erlang system. This flag is mandatory if the `-loader inet` flag is present.

SEE ALSO

`init(3)`, `erl_boot_server(3)`

erlang (Module)

By convention, Built In Functions (BIFs) are seen as being in the module `erlang`. Thus, both the calls `atom_to_list(Erlang)` and `erlang:atom_to_list(Erlang)` are identical.

BIFs may fail for a variety of reasons. All BIFs fail if they are called with arguments of an incorrect type. For example, `atom_to_list/1` will fail if it is called with an argument which is not an atom. If this type of failure is not within the scope of a catch (and the BIF is not called within a guard; see below), the process making the call will exit, and an EXIT signal with the associated reason `badarg` will be sent to all linked processes. The other reasons that may make BIFs fail are described in connection with the description of each individual BIF.

A few BIFs may be used in guard tests, for example:

```
tuple_5(Something) when size(Something) == 5 ->
    is_tuple_size_5;
tuple_5(_) ->
    is_something_else.
```

Here the BIF `size/1` is used in a guard. If `size/1` is called with a tuple, it will return the size of the tuple (i.e., how many elements there are in the tuple). In the above example, `size/1` is used in a guard which tests if its argument `Something` is a tuple and, if it is, whether it is of size 5. In this case, calling `size` with an argument other than a tuple will cause the guard to fail and execution will continue with the next clause.

Suppose `tuple_5/1` is written as follows:

```
tuple_5(Something) ->
    case size(Something) of
        5 -> is_tuple_size_5;
        _ -> is_something_else
    end.
```

In this case, `size/1` is not in a guard. If `Something` is not a tuple, `size/1` will fail and cause the process to exit with the associated reason `badarg` (see above).

Some of the BIFs in this chapter are optional in Erlang implementations, and not all implementations will include them.

The following descriptions indicate which BIFs can be used in guards and which BIFs are optional.

Exports

`abs(Number)`

Returns an integer or float which is the arithmetical absolute value of the argument Number (integer or float).

```
> abs(-3.33).  
3.33000  
> abs(-3).  
3
```

This BIF is allowed in guard tests.

Failure: `badarg` if the argument is not an integer or a float.

`apply({Module, Function}, ArgumentList)`

This is equivalent to `apply(Module, Function, ArgumentList)`.

`apply(Module, Function, ArgumentList)`

Returns the result of applying Function in Module on ArgumentList. The applied function must have been exported from Module. The arity of the function is the length of ArgumentList.

```
> apply(lists, reverse, [[a, b, c]]).  
[c,b,a]
```

`apply` can be used to evaluate BIFs by using the module name `erlang`.

```
> apply(erlang, atom_to_list, ['Erlang']).  
"Erlang"
```

Failure: `error_handler:undefined_function/3` is called if Module has not exported Function/Arity. The error handler can be redefined (see the BIF `process_flag/2`). If the `error_handler` is undefined, or if the user has redefined the default `error_handler` so the replacement module is undefined, an error with the reason `undef` will be generated.

`atom_to_list(Atom)`

Returns a list of integers (Latin-1 codes), which corresponds to the text representation of the argument Atom.

```
>atom_to_list('Erlang').  
"Erlang"
```

Failure: `badarg` if the argument is not an atom.

`binary_to_list(Binary)`

Returns a list of integers which correspond to the bytes of Binary.

`binary_to_list(Binary, Start, Stop)`

As `binary_to_list/1`, but it only returns the list from position Start to position Stop. Start and Stop are integers. Positions in the binary are numbered starting from 1.

`binary_to_term(Binary)`

Returns an Erlang term which is the result of decoding the binary `Binary`. `Binary` is encoded in the Erlang external binary representation. See `term_to_binary/1`.

`erlang:cancel_timer(Ref)`

`cancel_timer(Ref)` cancels a timer, where `Ref` was returned by either `send_after/3` or `start_timer/3`. If the timer was there to be removed, `cancel_timer/1` returns the time in ms left until the timer would have expired, otherwise `false` (which may mean that `Ref` was never a timer, or that it had already been cancelled, or that it had already delivered its message).

Note: usually, cancelling a timer does not guarantee that the message has not already been delivered to the message queue. However, in the special case of a process `P` cancelling a timer which would have sent a message to `P` itself, attempting to read the timeout message from the queue is guaranteed to remove the timeout in that situation:

```
cancel_timer(Ref),
receive
    {timeout, Ref, _} ->
        ok
    after 0 ->
        ok
end
```

Failure: `badarg` if `Ref` is not a reference.

`erlang:check_process_code(Pid, Module)`

Returns `true` if the process `Pid` is executing an old version of `Module`, if the current call of the process executes code for an old version of the module, if the process has references to an old version of the module, or if the process contains funs that references the old version of the module. Otherwise, it returns `false`.

```
> erlang:check_process_code(Pid, lists).
false
```

This is an optional BIF.

Failure: `badarg`, if the process argument is not a `Pid`, or the module argument is not an atom.

`concat_binary(ListOfBinaries)`

Concatenates a list of binaries `ListOfBinaries` into one binary.

`date()`

Returns the current date as `{Year, Month, Day}`

```
> date().
{1995, 2, 19}
```

erlang:delete_module(Module)

Moves the current version of the code of Module to the old version and deletes all export references of Module. Returns undefined if the module does not exist, otherwise true.

```
> delete_module(test).  
true
```

This is an optional BIF.

Failure: badarg if there is already an old version of the module (see BIF `purge_module/1`).

Warning:

In normal Erlang implementations code handling - which includes loading, deleting, and replacing modules - is performed in the module code. This BIF is intended for use with the implementation of the module code and should not be used elsewhere.

erlang:demonitor(Ref)

If Ref is a reference which the current process obtained by calling `erlang:monitor/2`, the monitoring is turned off.

It is an error if Ref refers to a monitoring started by another process. Not all such cases are cheap to check; if checking is cheap, the call fails with badarg (for example if Ref is a remote reference).

erlang:disconnect_node(Node)

Forces the disconnection of a node. This will appear to the node Node as if the current node has crashed. This BIF is mainly used in the Erlang network authentication protocols. Returns true if disconnection succeeds, otherwise false.

Failure: badarg if Node is not an atom.

element(N, Tuple)

Returns the Nth element (numbering from 1) of Tuple.

```
> element(2, {a, b, c}).  
b
```

Failure: badarg if N < 1, or N > size(Tuple), or if the argument Tuple is not a tuple.
Allowed in guard tests.

erase()

Returns the process dictionary and deletes it.

```
> put(key1, {1, 2, 3}), put(key2, [a, b, c]), erase().  
[{key1,{1, 2, 3}},{key2,[a, b, c]}]
```

erase(Key)

Returns the value associated with Key and deletes it from the process dictionary.
Returns undefined if no value is associated with Key. Key can be any Erlang term.

```
> put(key1, {merry, lambs, are, playing}),
   X = erase(key1), {X, erase(key1)}.
{{merry, lambs, are, playing}, undefined}
```

exit(Reason)

Stops the execution of the current process with the reason Reason. Can be caught. Reason is any Erlang term. Since evaluating this function causes the process to terminate, it has no return value.

```
> exit(foobar).
** exited: foobar **
> catch exit(foobar).
{'EXIT', foobar}
```

exit(Pid, Reason)

Sends an EXIT message to the process Pid. Returns true.

```
> exit(Pid, goodbye).
true
```

Note:

The above is not necessarily the same as:

```
Pid ! {'EXIT', self(), goodbye}
```

The above two alternatives are the same if the process with the process identity Pid is trapping exits. However, if Pid is not trapping exits, the Pid itself will exit and propagate EXIT signals in turn to its linked processes.

If the reason is the atom kill, for example `exit(Pid, kill)`, an untrappable EXIT signal will be sent to the process Pid. In other words, the process Pid will be unconditionally killed.

Returns true.

Failure: badarg if Pid is not a Pid.

fault(Reason)

Stops the execution of the current process with the reason Reason, where Reason is any Erlang term. The actual EXIT term will be {Reason, Where}, where Where is a list of the functions most recently called (the current function first). Since evaluating this function causes the process to terminate, it has no return value.

fault(Reason, Args)

Stops the execution of the current process with the reason Reason, where Reason is any Erlang term. The actual EXIT term will be {Reason, Where}, where Where is a list of the functions most recently called (the current function first). The Args is expected to be the arguments for the current function; in Beam it will be used to provide the actual arguments for the current function in the Where term. Since evaluating this function causes the process to terminate, it has no return value.

float(Number)

Returns a float by converting Number to a float.

```
> float(55).  
55.0000
```

Note:

float/1 is allowed in guard tests, but it tests whether the argument is a float or not.

```
-module(t).  
  
f(F) when float(F) -> float;  
f(F) -> not_a_float.  
  
1> t:f(1).  
not_a_float  
2> t:f(1.0).  
float  
3>
```

Failure: badarg if the argument is not a float or an integer.

erlang:fun_info(Fun)

Returns a list containing information about the fun Fun. In R6, the fun can be real fun type or the tuple representation; future versions will not allow the fun representation. This BIF is only intended for debugging. The list returned contains the following tuples, not necessarily in the order listed here (i.e. you should not depend on the order).

{id,Pid} Pid is the pid of the process that originally created the fun. It will be the atom undefined if the fun is given in the tuple representation.
{module,Module} Module (an atom) is the module in which the fun is defined.
{index,Index} Index (an integer) is an index into the module's fun table.
{index,Uniq} Uniq (an integer) is an unique value for this fun.
{env,Env} Env (a list) is the environment or free variables for the fun.

erlang:fun_info(Fun, Item)

Returns information about the Fun as specified by Item, in the form {Item, Info}. Item can be any of the atoms id, module, index, uniq, or env. See the erlang:fun_info/1 BIF.

erlang:fun_to_list(Fun)

Returns a textual representation of the fun Fun.

float_to_list(Float)

Returns a list of integers (ASCII codes) which corresponds to Float.

```
> float_to_list(7.0).
"7.000000000000000e+00"

Failure: badarg if the argument is not a float.
```

get()

Returns the process dictionary as a list of {Key, Value} tuples.

```
> put(key1, merry), put(key2, lambs),
   put(key3, {are, playing}), get().
[{key1, merry}, {key2, lambs}, {key3, {are, playing}}]
```

get(Key)

Returns the value associated with Key in the process dictionary, and undefined if no value is associated with Key. Key can be any Erlang term.

```
> put(key1, merry), put(key2, lambs),
   put({any, [valid, term]}, {are, playing}),
   get({any, [valid, term]}).
{are, playing}
```

erlang:get_cookie()

Returns the “magic cookie” of the current node, if the node is alive; otherwise the atom nocoookie.

get_keys(Value)

Returns a list of keys which corresponds to Value in the process dictionary.

```
> put(mary, {1, 2}), put(had, {1, 2}), put(a, {1, 2}),
   put(little, {1, 2}), put(dog, {1, 3}), put(lamb, {1, 2}),
   get_keys({1, 2}).
[mary, had, a, little, lamb]
```

group_leader()

Every process is a member of some process group and all groups have a leader.

This BIF returns the process identifier Pid of the group leader for the process which evaluates the BIF. When a process is spawned, the group leader of the spawned process is the same as that of the process which spawned it. Initially, at system start-up, init is both its own group leader and the group leader of all processes.

group_leader(Leader, Pid)

Sets the group leader of Pid to Leader. Typically, this is used when a processes started from a certain shell should have another group leader than init. The process Leader is normally a process with an I/O protocol. All I/O from this group of processes are thus channeled to the same place.

halt()

Halts the Erlang system and indicates normal exit to the calling environment. Has no return value.

```
> halt().  
unix_prompt%
```

halt(Status)

Status must be a non-negative integer, or a string. Halts the Erlang system. Has no return value. If Status is an integer, it is returned as an exit status of Erlang to the calling environment. If Status is a string, produces an Erlang crash dump with String as slogan, and then exits with a non-zero status code.

Note that on many platforms, only the status codes 0-255 are supported by the operating system.

erlang:hash(Term, Range)

Returns a hash value for Term within the range 1..Range.

hd(List)

Returns the first item of List.

```
> hd([1,2,3,4,5]).  
1
```

Allowed in guard tests.

Failure: badarg if List is the empty list [], or is not a list.

erlang:info(What)

This BIF is optional and may be removed or changed in future releases of Erlang. What can be any of the atoms info, procs, loaded, or dist. The BIF returns information of the different ‘topics’ as binary data objects.

Failure: badarg if What is not one of the atoms shown above.

integer_to_list(Integer)

Returns a list of integers (ASCII codes) which correspond to Integer.

```
> integer_to_list(77).  
"77"
```

Failure: badarg if the argument is not an integer.

is_alive()

Returns the atom true if the current node is alive; i.e., if the node can be part of a distributed system. Otherwise, it returns the atom false.

is_process_alive(Pid)

Pid must refer to a process on the current node. Returns the atom true if the process is alive, i.e., has not exited. Otherwise, it returns the atom false. This is the preferred way to check whether a process exists. Unlike process_info/[1,2], is_process_alive/1 does not report zombie processes as alive.

length(List)

Returns the length of List.

```
> length([1,2,3,4,5,6,7,8,9]).  
9
```

Allowed in guard tests.

Failure: `badarg` if the argument is not a proper list.

`link(Pid)`

Creates a link to the process (or port) `Pid`, if there is not such a link already. If a process attempts to create a link to itself, nothing is done. Returns `true`.

Failure: `badarg` if the argument is not a `Pid` or port. Sends the `EXIT` signal `noproc` to the process which evaluates `link` if the argument is the `Pid` of a process which does not exist.

`list_to_atom(CharArrayList)`

Returns an atom whose text representation is the integers (Latin-1 codes) in `CharArrayList`.

```
> list_to_atom([69, 114, 108, 97, 110, 103]).  
'Erlang'
```

Failure: `badarg` if the argument is not a list of integers, or if any integer in the list is not an integer in the range [0, 255].

`list_to_binary(ListOfIntegers)`

Returns a binary which is made from the integer list `ListOfIntegers`.

Failure: `badarg` if the argument is not a list of integers, or if any integer in the list is not an integer in the range [0, 255].

`list_to_float(AsciiIntegerList)`

Returns a float whose text representation is the integers (ASCII-values) in `AsciiIntegerList`.

```
> list_to_float([50,46,50,48,49,55,55,54,52,101,43,48]).  
2.20178
```

Failure: `badarg` if the argument is not a list of integers, or if `AsciiIntegerList` contains a bad representation of a float.

`list_to_integer(AsciiIntegerList)`

Returns an integer whose text representation is the integers (ASCII-values) in `AsciiIntegerList`.

```
> list_to_integer([49, 50, 51]).  
123
```

Failure: `badarg` if the argument is not a list of integers, or if `AsciiIntegerList` contains a bad representation of an integer.

`list_to_pid(AsciiIntegerList)`

Returns a Pid whose text representation is the integers (ASCII-values) in `AsciiIntegerList`. This BIF is intended for debugging, and in the Erlang operating system. *It should not be used in application programs.*

```
> list_to_pid("<0.4.1>").
<0.4.1>
```

Failure: `badarg` if the argument is not a list of integers, or `AsciiIntegerList` contains a bad representation of a Pid.

`list_to_tuple(List)`

Returns a tuple which corresponds to `List`. `List` can contain any Erlang terms.

```
> list_to_tuple([mary, had, a, little, {dog, cat, lamb}]).
{mary, had, a, little, {dog, cat, lamb}}
```

Failure: `badarg` if `List` is not a proper list.

`erlang:load_module(Module, Binary)`

If `Binary` contains the object code for the module `Module`, this BIF loads that object code. Also, if the code for the module `Module` already exists, all export references are replaced so they point to the newly loaded code. The previously loaded code is kept in the system as ‘old code’, as there may still be processes which are executing that code. It returns either `{module, Module}`, where `Module` is the name of the module which has been loaded, or `{error, Reason}` if load fails. `Reason` is one of the following:

`badfile` If the object code in `Binary` has an incorrect format.

`not_purged` If `Binary` contains a module which cannot be loaded because old code for this module already exists (see the BIFs `purge_module` and `delete_module`).

`badfile` If the object code contains code for another module than `Module`

Warning:

Code handling - which includes loading, deleting, and replacing of modules - is done by the module `code` in normal Erlang implementations. This BIF is intended for the implementation of the module named `code` and should not be used elsewhere.

This is an optional BIF.

Failure: `badarg` if the first argument is not an atom, or the second argument is not a binary.

`erlang:localtime()`

Returns the current local date and time `{{Year, Month, Day}, {Hour, Minute, Second}}` .

The time zone and daylight saving time correction depend on the underlying OS.

```
> erlang:localtime().
{{1996,11,6},{14,45,17}}
```

`erlang:localtime_to_universaltime(DateTime)`

Converts local date and time in `DateTime` to Universal Time Coordinated (UTC), if this is supported by the underlying OS. Otherwise, no conversion is done and `DateTime` is returned. The return value is of the form `{Year, Month, Day}, {Hour, Minute, Second}`.

Failure: `badarg` if the argument is not a valid date and time tuple `{Year, Month, Day}, {Hour, Minute, Second}`.

```
> erlang:localtime_to_universaltime({{1996,11,6},{14,45,17}}).
{{1996,11,6},{13,45,17}}
```

`make_ref()`

Returns an almost unique reference.

The returned reference will reoccur after approximately 2^{82} calls; therefore it is unique enough for most practical purposes.

```
> make_ref().
#Ref<0.0.0.135>
```

`erlang:module_loaded(Module)`

Returns the atom `true` if the module contained in atom `Module` is loaded, otherwise it returns the atom `false`. It does not attempt to load the module.

Warning:

This BIF is intended for the implementation of the module named `code` and should not be used anywhere else. Use `code:is_loaded/1` instead.

```
> erlang:module_loaded(lists).
true
```

This is an optional BIF.

Failure: `badarg` if the argument is not an atom.

`erlang:monitor(Type, Item)`

The current process starts monitoring `Item`, and will be notified when `Item` dies, with a message `{'DOWN', Ref, Type, Item, Info}`, where `Ref` is the value returned by the call to `erlang:monitor/2`, and `Info` gives additional information. The message is also sent if `Item` is already dead. The value returned can be used for disabling the monitor (see `erlang:demonitor/1`).

The currently allowed arguments are the atom `process` for `Type`, and a pid for `Item`; `Info` in the message is the exit reason of the process (or `noproc` or `noconnection`, when the process does not exist or the remote node goes down, respectively, in analogy with `link/1`). If an attempt is made to monitor a process on an older node (where remote process monitoring is not implemented), the call fails with `badarg`.

Making several calls to `erlang:monitor/2` for the same item is not an error; it results in several completely independent monitorings.

`monitor_node(Node, Flag)`

Monitors the status of the node `Node`. If `Flag` is `true`, monitoring is turned on; if `Flag` is `false`, monitoring is turned off. Calls to the BIF are accumulated. This is shown in the following example, where a process is already monitoring the node `Node` and a library function is called:

```
monitor_node(Node, true),  
    ... some operations  
monitor_node(Node, false),
```

After the call, the process is still monitoring the node.

If `Node` fails or does not exist, the message `{nodedown, Node}` is delivered to the process. If a process has made two calls to `monitor_node(Node, true)` and `Node` terminates, two `nodedown` messages are delivered to the process. If there is no connection to `Node`, there will be an attempt to create one. If this fails, a `nodedown` message is delivered.

Returns `true`.

Failure: `badarg` if `Flag` is not `true` or `false`, and `badarg` if `Node` is not an atom indicating a remote node, or if the local node is not alive.

`node()`

Returns the name of the current node. If it is not a networked node but a local Erlang system, the atom `nonode@nohost` is returned.

Allowed in guard tests.

`node(Arg)`

Returns the node where `Arg` is located. `Arg` can be a Pid, a reference, or a port.

Allowed in guard tests.

Failure: `badarg` if `Arg` is not a Pid, reference, or port.

`nodes()`

Returns a list of all known nodes in the system, excluding the current node.

`now()`

Returns the tuple `{MegaSecs, Secs, Microsecs}`

which is the elapsed time since 00:00 GMT, January 1, 1970 (zero hour) on the assumption that the underlying OS supports this. Otherwise, some other point in time is chosen. It is also guaranteed that subsequent calls to this BIF returns continuously increasing values. Hence, the return value from `now()` can be used to generate unique time-stamps. It can only be used to check the local time of day if the time-zone info of the underlying operating system is properly configured.

`open_port(PortName, PortSettings)`

Returns a port identifier as the result of opening a new Erlang port. A port can be seen as an external Erlang process. `PortName` is one of the following:

{spawn, Command} Starts an external program. Command is the name of the external program which will be run. Command runs outside the Erlang work space unless an Erlang driver with the name Command is found. If found, that driver will be started. A driver runs in the Erlang workspace, which means that it is linked with the Erlang runtime system.

When starting external programs on Solaris, the system call `vfork` is used in preference to `fork` for performance reasons, although it has a history of being less robust. If there are problems with using `vfork`, setting the environment variable `ERL_NO_VFORK` to any value will cause `fork` to be used instead.

`Atom` *This use of `open_port()` is obsolete and will be removed in a future version of Erlang. Use the `file` module instead.* The atom is assumed to be the name of an external resource. A transparent connection is established between Erlang and the resource named by the atom Atom. The characteristics of the port depend on the type of resource. If Atom represents a normal file, the entire contents of the file is sent to the Erlang process as one or more messages. When messages are sent to the port, it causes data to be written to the file.

{fd, In, Out} Allows an Erlang process to access any currently opened file descriptors used by Erlang. The file descriptor In can be used for standard input, and the file descriptor Out for standard output. It is only used for various servers in the Erlang operating system (`shell` and `user`). Hence, its use is very limited.

`PortSettings` is a list of settings for the port. Valid values are:

{packet, N} Messages are preceded by their length, sent in N bytes, with the most significant byte first. Valid values for N are 1, 2, or 4.

stream Output messages are sent without packet lengths. A user-defined protocol must be used between the Erlang process and the external object.

{line, N} Messages are delivered on a per line basis. Each line (delimited by the OS-dependent newline sequence) is delivered in one single message. The message data format is {Flag, Line}, where Flag is either `eol` or `noeol` and Line is the actual data delivered (without the newline sequence).

N specifies the maximum line length in bytes. Lines longer than this will be delivered in more than one message, with the Flag set to `noeol` for all but the last message. If end of file is encountered anywhere else than immediately following a newline sequence, the last line will also be delivered with the Flag set to `noeol`. In all other cases, lines are delivered with Flag set to `eol`.

The {packet, N} and {line, N} settings are mutually exclusive.

{cd, Dir} This is only valid for {spawn, Command}. The external program starts using Dir as its working directory. Dir must be a string. Not available on VxWorks.

{env, Environment} This is only valid for {spawn, Command}. The environment of the started process is extended using the environment specifications in Environment. Environment should be a list of tuples {Name, Value}, where Name is the name of an environment variable, and Value is the value it is to have in the spawned port process. Both Name and Value must be strings. The one exception is Value being the atom `false` (in analogy with `os:getenv/1`), which removes the environment variable. Not available on VxWorks.

`exit_status` This is only valid for {spawn, Command} where Command refers to an external program. When the external process connected to the port exits, a message of the form {Port, {exit_status, Status}} is sent to the connected process, where Status is the exit status of the external process. If the program aborts, on Unix the same convention is used as the shells do (i.e. 128+signal). If

the `eof` option has been given as well, the `eof` message and the `exit_status` message appear in an unspecified order. If the port program closes its `stdout` without exiting, the `exit_status` option will not work.

`use_stdio` This is only valid for `{spawn, Command}`. It allows the standard input and output (file descriptors 0 and 1) of the spawned (UNIX) process for communication with Erlang.

`nouse_stdio` The opposite of the above. Uses file descriptors 3 and 4 for communication with Erlang.

`stderr_to_stdout` Affects ports to external programs. The executed program gets its standard error file redirected to its standard output file. `stderr_to_stdout` and `nouse_stdio` are mutually exclusive.

`in` The port can only be used for input.

`out` The port can only be used for output.

`binary` All I/O from the port are binary data objects as opposed to lists of bytes.

`eof` The port will not be closed at the end of the file and produce an EXIT signal.

Instead, it will remain open and a `{Port, eof}` message will be sent to the process holding the port.

The default is `stream` for all types of port and `use_stdio` for spawned ports.

Failure: `badarg` if the format of `PortName` or `PortSettings` is incorrect. If the port cannot be opened, the exit reason is the Posix error code which most closely describes the error, or `eINVAL` if no Posix code is appropriate. The following Posix error codes may appear:

`ENOMEM` There was not enough memory to create the port.

`EAGAIN` There are no more available operating system processes.

`ENAMETOOLONG` The external command given was too long.

`EMFILE` There are no more available file descriptors.

`ENFILE` A file or port table is full.

During use of a port opened using `{spawn, Name}`, errors arising when sending messages to it are reported to the owning process using exit signals of the form `{'EXIT', Port, PosixCode}`. Posix codes are listed in the documentation for the `file` module.

`pid_to_list(Pid)`

Returns a list which corresponds to the process `Pid`.

Warning:

This BIF is intended for debugging and for use in the Erlang operating system. It should not be used in application programs.

```
> pid_to_list(whereis(init)).  
"<0.0.0>"
```

Failure: `badarg` if the argument is not a `Pid`.

`erlang:port_info(Port, Item)`

Returns information about the port `Port` as specified by `Item`, which can be any one of the atoms `id`, `connected`, `links`, `name`, `input`, or `output`.

`{id, Index}` `Index` is the internal index of the port. This index may be used to separate ports.

`{connected, Pid}` `Pid` is the process connected to the port.

`{links,ListOfPids}` `ListofPids` is a list of `Pids` with processes to which the port has a link.

`{name, String}` `String` is the command name set by `open_port`.

`{input, Bytes}` `Bytes` is the total number of bytes read from the port.

`{output, Bytes}` `Bytes` is the total number of bytes written to the port.

All implementations may not support all of the above `Items`. Returns `undefined` if the port does not exist.

Failure: `badarg` if `Port` is not a process identifier, or if `Port` is a port identifier of a remote process.

`erlang:ports()`

Returns a list of all ports on the current node.

`erlang:pre_loaded()`

Returns a list of Erlang modules which are pre-loaded in the system. As all loading of code is done through the file system, the file system must have been loaded previously. Hence, at least the module `init` must be pre-loaded.

`erlang:process_display(Pid, Type)`

Writes information about the local process `Pid` on standard error. The currently allowed value for the atom `Type` is `backtrace`, which shows the contents of the stack, including information about the call chain, with the most recent data printed last. The format of the output is not further defined. `Pid` may be a zombie process.

`process_flag(Flag, Option)`

Sets certain flags for the process which calls this function. Returns the old value of the flag.

`process_flag(trap_exit, Boolean)` When `trap_exit` is set to `true`, `EXIT` signals arriving to a process are converted to `{'EXIT', From, Reason}` messages, which can be received as ordinary messages. If `trap_exit` is set to `false`, the process exits if it receives an `EXIT` signal other than `normal` and the `EXIT` signal is propagated to its linked processes. Application processes should normally not trap exits.

`process_flag(error_handler, Module)` This is used by a process to redefine the error handler for undefined function calls and undefined registered processes.

Inexperienced users should not use this flag since code autoloading is dependent on the correct operation of the error handling module.

`process_flag(priority, Level)` This sets the process priority. `Level` is an atom. All implementations support three priority levels, `low`, `normal`, and `high`. The default is `normal`.

`process_flag(save_calls, N)` `N` must be an integer in the interval [0, 10000]. If `N > 0`, call saving is made active for the process, which means that information about the `N` most recent global function calls, BIF calls, sends and receives made by the process are saved in a list, which can be retrieved with `process_info(Pid, last_calls)`. A global function call is one in which the module of the function is explicitly mentioned. Only a fixed amount of information is saved: a tuple `{Module, Function, Arity}` for function calls, and the mere atoms `send`, `'receive'` and `timeout` for sends and receives (`'receive'` when a message is received and `timeout` when a receive times out). If `N = 0`, call saving is disabled for the process. Whenever the size of the call saving list is set, its contents are reset.

Failure: `badarg` if `Flag` is not an atom, or is not a recognized flag value, or if `Option` is not a recognized term for `Flag`.

`process_flag(Pid, Flag, Option)`

Sets certain flags for the process `Pid`, in the same manner as `process_flag/2`. Returns the old value of the flag. The allowed values for `Flag` are only a subset of those allowed in `process_flag/2`, namely: `save_calls`.

Failure: `badarg` if `Pid` is not a process on the local node, or if `Flag` is not an atom, or is not a recognized flag value, or if `Option` is not a recognized term for `Flag`.

`process_info(Pid)`

Returns a long list which contains information about the process `Pid`. This BIF is only intended for debugging. It should not be used for any other purpose. The list returned contains the following tuples. The order in which these tuples are returned is not defined, nor are all the tuples mandatory.

- `{current_function, {Module, Function, Arguments}}` `Module, Function, Arguments` is the current function call of the process.
- `{dictionary, Dictionary}` `Dictionary` is the dictionary of the process.
- `{error_handler, Module}` `Module` is the error handler module used by the process (for undefined function calls, for example).
- `{group_leader, Groupleader}` `Groupleader` is group leader for the I/O of the process.
- `{heap_size, Size}` `Size` is the heap size of the process in heap words.
- `{initial_call, {Module, Function, Arity}}` `Module, Function, Arity` is the initial function call with which the process was spawned.
- `{links, ListOfPids}` `ListOfPids` is a list of Pids, with processes to which the process has a link.
- `{message_queue_len, MessageQueueLen}` `MessageQueueLen` is the number of messages currently in the message queue of the process. This is the length of the list `MessageQueue` returned as the info item `messages` (see below).
- `{messages, MessageQueue}` `MessageQueue` is a list of the messages to the process, which have not yet been processed.
- `{priority, Level}` `Level` is the current priority level for the process. Only `low` and `normal` are always supported.
- `{reductions, Number}` `Number` is the number of reductions executed by the process.

{registered_name, Atom} Atom is the registered name of the process. If the process has no registered name, this tuple is not present in the list.

{stack_size, Size} Size is the stack size of the process in stack words.

{status, Status} Status is the status of the process. Status is waiting (waiting for a message), running, runnable (ready to run, but another process is running), suspended (suspended on a “busy” port or by the trace/3 BIF), or exiting (if the process has exited, but remains as a zombie).

{trap_exit, Boolean} Boolean is true if the process is trapping exits, otherwise it is false.

Failure: badarg if the argument is not a Pid, or if Pid is a Pid of a remote process.

`process_info(Pid, Item)`

Returns information about the process Pid as specified by Item, in the form {Item, Info}. Item can be any one of the atoms backtrace, current_function, dictionary, error_handler, exit, group_leader, heap_size, initial_call, last_calls, links, memory, message_queue_len, messages, priority, reductions, registered_name, stack_size, status or trap_exit.

Returns undefined if no information is known about the process.

`process_info` can be used to obtain information about processes which have exited but whose data are still kept, so called zombie processes. To determine whether to keep information about dead processes, use the BIF `erlang:system_flag/2`. Since `process_info` does not necessarily return undefined for a dead process, use `is_process_alive/1` to check whether a process is alive.

Item `exit` returns [] if the process is alive, or {exit, Reason} if the process has exited, where Reason is the exit reason.

Item `registered_name` returns [] if the process has no registered name. If the process is a zombie, the registered name it had when it died is returned.

Item `memory` returns {memory, Size}, where Size is the size of the process in bytes. This includes stack, heap and internal structures.

Item `backtrace` returns a binary, which contains the same information as the output from `erlang:process_display(Pid, backtrace)`. Use `binary_to_list/1` to obtain the string of characters from the binary.

Item `last_calls` returns false if call saving is not active for the process (see `process_flag/3` [page 82]). If call saving is active, a list is returned, in which the last element is the most recent.

Not all implementations support every one of the above Items.

Failure: badarg if Pid is not a process identifier, or if Pid is a process identifier of a remote process.

`processes()`

Returns a list of all processes on the current node, including zombie processes. See `system_flag/2` [page 89].

```
> processes().
[<0.0.1>, <0.1.1>, <0.2.1>, <0.3.1>, <0.4.1>, <0.6.1>]
```

`erlang:purge_module(Module)`

Removes old code for Module. Before this BIF is used, `erlang:check_process_code/2` should be called to check that no processes are executing old code in this module.

Warning:

In normal Erlang implementations, code handling - which is loading, deleting and replacing modules - is evaluated by the module code. This BIF is intended to be used by the implementation of the module code and should not be used in any other place.

This is an optional BIF.

Failure: badarg if Module does not exist.

`put(Key, Value)`

Adds a new Value to the process dictionary and associates it with Key. If a value is already associated with Key, that value is deleted and replaced by the new value Value. It returns any value previously associated with Key, or undefined if no value was associated with Key. Key and Value can be any valid Erlang terms.

Note:

The values stored when put is evaluated within the scope of a catch will not be retracted if a throw is evaluated, or if an error occurs.

```
> X = put(name, walrus), Y = put(name, carpenter),
   Z = get(name),
   {X, Y, Z}.
{undefined, walrus, carpenter}
```

`register(Name, Pid)`

Associates the name Name with the process identity Pid. Name, which must be an atom, can be used instead of a pid in the send operator (Name ! Message).

Returns true.

Failure: badarg if Pid is not an active process, or if Pid is a process on another node, or if the name Name is already in use, or if the process is already registered (it already has a name), or if the name Name is not an atom, or if Name is the atom undefined.

`registered()`

Returns a list of names which have been registered using register/2.

```
> registered().
[code_server, file_server, init, user, my_db]
```

`erlang:resume_process(Pid)`

Resume a suspended process. This should be used for debugging purposes only, not in production code.

`round(Number)`

Returns an integer by rounding the number `Number`. Allowed in guard tests.

```
> round(5.5).  
6
```

Failure: `badarg` if the argument is not a float (or an integer).

`self()`

Returns the process identity of the calling process. Allowed in guard tests.

```
> self().  
<0.16.1>
```

`erlang:send_after(Time, Pid, Msg)`

`Time` is a non-negative integer, `Pid` is either a pid or an atom, and `Msg` is any Erlang term. The function returns a reference.

After `Time` ms, `send_after/3` sends `Msg` to `Pid`.

If `Pid` is an atom, it is supposed to be the name of a registered process. The process referred to by the name is looked up at the time of delivery. No error is given if the name does not refer to a process. See also `start_timer/3` and `cancel_timer/1`.

Limitations: `Pid` must be a process on the local node. The timeout value must fit in 32 bits.

Failure: `badarg` if any arguments are of the wrong type, or do not obey the limitations noted above.

`erlang:set_cookie(Node, Cookie)`

Sets the “magic cookie” of `Node` to the atom `Cookie`. If `Node` is the current node, the BIF also sets the cookie of all other unknown nodes to `Cookie` (see `auth(3)`).

`setelement(Index, Tuple, Value)`

Returns a tuple which is a copy of the argument `Tuple` with the element given by the integer argument `Index` (the first element is the element with index 1) replaced by the argument `Value`.

```
> setelement(2, {10, green, bottles}, red).  
{10, red, bottles}
```

Failure: `badarg` if `Index` is not an integer, or `Tuple` is not a tuple, or if `Index` is less than 1 or greater than the size of `Tuple`.

`size(Item)`

Returns an integer which is the size of the argument `Item`, where `Item` must be either a tuple or a binary.

```
> size({morni, mulle, bwange}).  
3
```

Allowed in guard tests.

Failure: `badarg` if `Item` is not a tuple or a binary.

spawn(Fun)

Returns the Pid of a new process started by the application of Fun to the empty argument list []. Otherwise works like spawn/3.

spawn(Node, Fun)

Returns the Pid of a new process started by the application of Fun to the empty argument list [] on node Node. Otherwise works like spawn/4.

spawn(Module, Function, ArgumentList)

Returns the Pid of a new process started by the application of Module:Function to ArgumentList. *Note:* The new process created will be placed in the system scheduler queue and will be run some time later.

`error_handler:undefined_function(Module, Function, ArgumentList)` is evaluated by the new process if `Module:Function/A`rity does not exist (where Arity is the length of ArgumentList). The error handler can be redefined (see BIF `process_flag/2`). Arity is the length of the ArgumentList. If `error_handler` is undefined, or the user has redefined the default `error_handler` so its replacement is undefined, a failure with the reason `undef` will occur.

```
> spawn(speed, regulator, [high_speed, thin_cut]).  
<0.13.1>
```

Failure: badarg if Module and/or Function is not an atom, or if ArgumentList is not a list.

spawn(Node, Module, Function, ArgumentList)

Works like spawn/3, with the exception that the process is spawned at Node. If Node does not exist, a useless Pid is returned.

Failure: badarg if Node, Module, or Function are not atoms, or ArgumentList is not a list.

spawn_link(Fun)

Works like spawn/1 except that a link is made from the current process to the newly created one, atomically.

spawn_link(Node, Fun)

Works like spawn/2 except that a link is made from the current process to the newly created one, atomically.

spawn_link(Module, Function, ArgumentList)

This BIF is identical to the following code being evaluated in an atomic operation:

```
> Pid = spawn(Module, Function, ArgumentList),  
    link(Pid),  
    Pid.
```

This BIF is necessary since the process created might run immediately and fail before link/1 is called.

Failure: See spawn/3.

`spawn_link(Node, Module, Function, ArgumentList)`

Works like `spawn_link/3`, except that the process is spawned at `Node`. If an attempt is made to spawn a process on a node which does not exist, a useless Pid is returned, and an EXIT signal will be received.

`spawn_opt(Module, Function, ArgumentList, Options)`

Works exactly like `spawn/3`, except that the following options can be given when creating the process:

`link` Sets a link to the parent process (`link spawn_link/3` does).

`{priority, Level}` Sets the priority of the new process. Equivalent to executing `process_flag(priority, Level)` in the start function of the new process, except that the priority will be set before the process is scheduled in the first time.

`{gc_switch, Threshold}` Sets the garbage collection strategy for the new process. If `Threshold` is 0, generational garbage collection will be used (this is default). If `Threshold` is greater than zero, the fullsweep algorithm will be used until the amount of live data (counted in words) reaches `Threshold`, at which point generational collection will be used. A large `Threshold` or the atom infinity means the fullsweep algorithm will be used.

Note: Generation collection is generally faster, especially for processes with a large amount of live data, but requires more memory since two heaps are allocated.

`{min_heap_size, Size}` Gives a minimum heap size in words. Setting this value higher than the system default might speed up some processes because less garbage collection is done. Setting too high value, however, might waste memory and slow down the system due to worse data locality. Therefore, it is recommended to use this option only for fine-tuning an application and to measure the execution time with various `Size` values.

`split_binary(Binary, Pos)`

Returns a tuple which contains two binaries which are the result of splitting `Binary` into two parts at position `Pos`. This is not a destructive operation. After this operation, there are three binaries altogether. Returns a tuple consisting of the two new binaries. For example:

```
1> B = list_to_binary("0123456789").
#Bin
2> size(B).
10
3> {B1, B2} = split_binary(B,3).
{#Bin, #Bin}
4> size(B1).
3
5> size(B2).
7
```

Failure: badarg if Binary is not a binary, or Pos is not an integer or is out of range.

erlang:start_timer(Time, Pid, Msg)

Time is a non-negative integer, Pid is either a pid or an atom, and Msg is any Erlang term. The function returns a reference.

After Time ms, start_timer/3 sends the tuple {timeout, Ref, Msg} to Pid, where Ref is the reference returned by start_timer/3.

If Pid is an atom, it is supposed to be the name of a registered process. The process referred to by the name is looked up at the time of delivery. No error is given if the name does not refer to a process. See also send_after/3 and cancel_timer/1.

Limitations: Pid must be a process on the local node. The timeout value must fit in 32 bits.

Failure: badarg if any arguments are of the wrong type, or do not obey the limitations noted above.

statistics(Type)

Returns information about the system. Type is an atom which is one of:

run_queue Returns the length of the run queue, that is the number of processes that are ready to run.

runtime Returns {Total_Run_Time, Time_Since_Last_Call}.

wall_clock Returns {Total_Wallclock_Time, Wallclock.Time_Since_Last_Call}. wall_clock can be used in the same manner as the atom runtime, except that real time is measured as opposed to runtime or CPU time.

reductions Returns {Total_Reductions, Reductions_Since_Last_Call}.

garbage_collection Returns {Number_of_GCs, Words_Reclaimed, 0}. This information may not be valid for all implementations.

All times are in milliseconds.

```
> statistics(runtime).  
{1690, 1620}  
> statistics(reductions).  
{2046, 11}  
> statistics(garbage_collection).  
{85, 23961, 0}
```

Failure: badarg if Type is not one of the atoms shown above.

erlang:suspend_process(Pid)

Suspend a process. This should be used for debugging purposes only, not in production code.

erlang:system_flag(Flag, Value)

This BIF sets various system properties of the Erlang node. If Flag is a valid name of a system flag, its value is set to Value, and the old value is returned.

The currently allowed value for Flag is `keep_zombies`. The value of the `keep_zombies` flag is an integer which indicates how many processes to keep in memory when they exit, so that they can be inspected with `process_info`. Originally, the number is 0. Setting it to 0 disables the keeping of zombies. A negative number `-N` means to keep the `N` latest zombies; a positive value `N` means to keep the `N` first zombies. Setting the flag always clears away any already saved zombies. The maximum number of zombies which can be saved is 100. Resources owned by a zombie process are cleared away immediately when the process dies, for example ets tables and ports, and cannot be inspected.

`term_to_binary(Term)`

This BIF returns the encoded value of any Erlang term and turns it into the Erlang external term format. It can be used for a variety of purposes, for example writing a term to a file in an efficient way, or sending an Erlang term to some type of communications channel not supported by distributed Erlang.

Returns a binary data object which corresponds to an external representation of the Erlang term `Term`.

`throw(Any)`

A non-local return from a function. If evaluated within a `catch`, `catch` will return the value `Any`.

```
> catch throw({hello, there}).  
{hello, there}
```

Failure: `nocatch` if not evaluated within a `catch`.

`time()`

Returns the tuple `{Hour, Minute, Second}` of the current system time. The time zone correction is implementation-dependent.

```
> time().  
{9, 42, 44}
```

`tl(List)`

Returns `List` stripped of its first element.

```
> tl([geesties, guilies, beasties]).  
[guilies, beasties]
```

Failure: `badarg` if `List` is the empty list `[]`, or is not a list. Allowed in guard tests.

`erlang:trace(PidSpec, How, Flaglist)`

Turns on (if `How == true`) or off (if `How == false`) the trace flags in `Flaglist` for the process or processes represented by `PidSpec`. `PidSpec` is either a pid for a local process, or one of the following atoms:

`existing` All processes currently existing.

`new` All processes that will be created in the future.

`a11` All currently existing processes and all processes that will be created in the future.

Flaglist can contain any number of the following atoms (the “message tags” refers to the list of message following below):

`send` Traces the messages the process Pid sends. Message tags: `send`,
`send_to_non_existing_process`.

`'receive'` Traces the messages the process Pid receives. Message tags: `'receive'`.

`procs` Traces process related events, for example `spawn`, `link`, `exit`. Message tags:
`spawn`, `exit`, `link`, `unlink`, `getting_linked`.

`call` Traces external function calls to external functions that tracing have been enabled for. Use the `erlang:trace_pattern/2` [page 92] BIF to enable tracing for external functions. Message tags: `call`, `return`.

`old_call_trace` Traces function calls. This flag only works for code that has been trace-compiled. Message tags: `call`, `return`.

This flag will be removed in a future version. Its functionality will be provided in a different way.

`running` Traces scheduling of processes. Message tags: `in`, `out`.

`garbage_collection` Traces garbage collections of processes. Message tags: `gc_start`,
`gc_end`.

`timestamp` Make a time stamp in all trace messages. The time stamp (`Ts`) is of the same form as returned by `erlang:now()`.

`arity` Instead of `{Mod, Fun, Args}` in call traces, there will be `{Mod, Fun, Arity}`.

`set_on_spawn` Makes any process created by Pid inherit the flags of Pid, including the `set_on_spawn` flag.

`set_on_first_spawn` Makes the first process created by Pid inherit the flags of Pid
That process does not inherit the `set_on_first_spawn` flag.

`set_on_link` Makes any process linked by Pid inherit the flags of Pid, including the `set_on_link` flag.

`set_on_first_link` Makes the first process linked to by Pid inherit the flags of Pid.
That process does not inherit the `set_on_first_link` flag.

`{tracer, Tracer}` Tracer should be the pid for a local process or the port identifier for a local port. All trace messages will be sent to the given process or port. If this flag is not given, trace messages will be sent to the process that called `erlang:trace/3`.

The effect of combining `set_on_first_link` with `set_on_link` is the same as having `set_on_first_link` alone. Likewise for `set_on_spawn` and `set_on_first_spawn`.

If the `timestamp` flag is not given, the tracing process will receive the trace messages described below. If the `timestamp` flag is given, the first element of the tuple will be `trace_ts` and the timestamp will be in the last element of the tuple.

`{trace, Pid, 'receive', Message}` When the traced Pid receives something.

`{trace, Pid, send, Msg, To}` When Pid sends a message.

`{trace, Pid, send_to_non_existing_process, Msg, To [,Ts]}` When Pid sends a message to a non existing process.

`{trace, Pid, call, {M,F,A}}` When Pid makes a function/BIF call. The return values of calls are never supplied, only the call and its arguments.

{trace, Pid, return_to, {M,F,A}} When Pid returns *to* function {M,F,A}. This trace message is only sent when both the old_call_trace and timestamp flags have been given.

{trace, Pid, return_from, {M,F,A}, ReturnValue} When Pid returns *from* the function {M,F,A} This trace message is sent when the call flag has been specified, and the function has a match specification with a return_trace action.

{trace, Pid, spawn, Pid2} When Pid spawns a new process Pid2.

{trace, Pid, exit, Reason} When Pid exits with reason Reason.

{trace, Pid, link, Pid2} When Pid links to a process Pid2.

{trace, Pid, unlink, Pid2} When Pid removes the link from a process Pid2.

{trace, Pid, getting_linked, Pid2} When Pid gets linked to a process Pid2.

{trace, Pid, in, {M,F,A}} When Pid is scheduled to run. The process will run in function {M,F,A}, where A is always the arity.

{trace, Pid, out, {M,F,A}} When Pid is scheduled out. The process was running in function {M,F,A} where A is always the arity.

{trace, Pid, gc_start, Info} Sent when garbage collection is about to be started. Info is a list of two-element tuples, where the first element is a key, and the second is the value. You should not depend on the tuples have any defined order. Currently, the following keys are defined.

- heap_size The size of the used part of the heap.
- old_heap_size The size of the used part of the old heap.
- stack_size The actual size of the stack.
- recent_size The size of the data that survived the previous garbage collection.
- mbuf_size The combined size of message buffers associated with the process.

All sizes are in words.

{trace, Pid, gc_end, Info} Sent when garbage collection is finished. Info contains the same kind of list as in the gc_start message, but the sizes reflect the new sizes after garbage collection.

If the tracing process dies, the flags will be silently removed.

Only one process can trace a particular process. For this reason, attempts to trace an already traced process will fail.

Returns: A number indicating the number of processes that matched PidSpec. If PidSpec is a pid, the return value will be 1. If PidSpec is all or existing the return value will be the number of processes running, excluding tracer processes. If PidSpec is new, the return value will be 0.

Failure: badarg if bad arguments are given.

```
erlang:trace_info(PidOrFunc, Item)
```

Returns trace information about a process or exported function.

To get information about a process, PidOrFunc should be a pid or the atom new. The atom new means that the default trace state for processes to be created will be returned. Item must have one of the following values:

flags Return a list of atoms indicating what kind of traces is enabled for the process.

The list will be empty if no traces are enabled, and one or more of the followings atoms if traces are enabled: `send`, `'receive'`, `set_on_spawn`, `call`, `old_call_trace`, `procs`, `set_on_first_spawn`, `set_on_link`, `running`, `garbage_collection`, `timestamp`, and `arity`. The order is arbitrary.

tracer Return the identifier for process or port tracing this process. If this process is not being traced, the return value will be `[]`.

To get information about an exported function, `PidOrFunc` should be three-element tuple: `{Module, Function, Arity}`. No wildcards are allowed. `Item` must have one of the following values:

traced Return `true` if this function is traced or `false` otherwise.

match_spec Return the match specification for this function, if it has one. If the function is not traced or if there is no match specification, an empty list will be returned.

The return value will be `{Item, Value}`, where `Value` is the requested information as described above. If a pid for a dead process was given, or the name of a non-existing function, the return value will be `undefined`.

`erlang:trace_pattern(MFA, MatchSpec)`

This BIF is used to enable or disable call tracing for exported functions. It must be combined with `erlang:trace/3` [page 89] to set the `call` trace flag for one or more processes.

Conceptually, call tracing works like this. Inside the Erlang virtual machine there is a set of processes to be traced and a set of functions to be traced. Tracing will be enabled on the intersection of the set. That is, if a process included in the traced process set calls a function included in the traced function set, the trace action will be taken. Otherwise, nothing will happen.

Use `erlang:trace/3` [page 89] to add or remove one or more processes to the set of traced processes. Use `erlang:trace_pattern/2` to add or remove exported functions to the set of traced functions.

The `erlang:trace_pattern/2` BIF can also add match specifications to an exported function. A match specification comprises a pattern that the arguments to the function must match, a guard expression which must evaluate to `true` and action to be performed. The default action is to send a trace message. If the pattern doesn't match or the guard fails, the action will not be executed.

The `MFA` argument should be a tuple like `{Module, Function, Arity}`. It can be the module, function, and arity for an exported function (or a BIF in any module). The `'_'` atom can be used to mean any of that kind. Wildcards can be used in any of the following ways:

`{Mod, Func, '_'}` All exported functions of any arity named `Func` in module `Mod`.

`{Mod, '_', '_'`} All exported functions in module `Mod`.

`{'_', '_', '_'`} All exported functions in all loaded modules.

Other combinations, such as `{Mod, '_', Arity}`, are not allowed. Local functions will not match any wildcard.

The `MatchSpec` argument can any of the following forms:

`false` Disable tracing for the matching exported function(s). Any match specification will be removed.

`true` Enable tracing for the matching exported function(s).

`MatchSpecList` A list of match specifications. An empty list is equivalent to `true`. See the ERTS User's Guide for a description of match specifications.

There is no way to directly change part of a match specification list. If a function has a match specification, you can replace it with a completely new one. If you need to change an existing match specification, use the `erlang:trace_info/2` [page 91] BIF to retrieve the existing match specification.

Returns the number of exported functions that matched the MFA argument. This will be zero if none matched at all.

Failure: `badarg` for invalid MFA or MatchSpec.

`trunc(Number)`

Returns an integer by the truncation of Number. Allowed in guard tests.

```
> trunc(5.5).
```

```
5
```

Failure: `badarg` if the argument is not a float, or an integer.

`tuple_to_list(Tuple)`

Returns a list which corresponds to Tuple. Tuple may contain any valid Erlang terms.

```
> tuple_to_list({share, {'Ericsson_B', 163}}).
[share, {'Ericsson_B', 163}]
```

Failure: `badarg` if the argument is not a tuple.

`erlang:universaltime()`

Returns the current date and time according to Universal Time Coordinated (UTC), also called GMT, in the form `{Year, Month, Day}, {Hour, Minute, Second}` if supported by the underlying operating system. If not, `erlang:universaltime()` is equivalent to `erlang:localtime()`.

```
> erlang:universaltime().
{{1996,11,6},{14,18,43}}
```

`erlang:universaltime_to_localtime(DateTime)`

Converts UTC date and time in DateTime to local date and time if supported by the underlying operating system. Otherwise, no conversion is done, and DateTime is returned. The return value is of the form `{Year, Month, Day}, {Hour, Minute, Second}`.

Failure: `badarg` if the argument is not a valid date and time tuple `{Year, Month, Day}, {Hour, Minute, Second}`.

```
> erlang:universaltime_to_localtime({{1996,11,6},{14,18,43}}).
{{1996,11,7},{15,18,43}}
```

`unlink(Pid)`

Removes a link, if there is one, from the calling process to another process given by the argument `Pid`.

Returns `true`. Will not fail if not linked to `Pid`, or if `Pid` does not exist.

Failure: `badarg` if the argument is not a valid `Pid`.

`unregister(Name)`

Removes the registered name for a process, given by the atom argument `Name`.

Returns the atom `true`.

```
> unregister(db).  
true
```

Failure: `badarg` if `Name` is not the name of a registered process.

Users are advised not to unregister system processes.

`whereis(Name)`

Returns the `Pid` for the process registered under `Name` (see `register/2`). Returns `undefined` if no such process is registered.

```
> whereis(user).  
<0.3.1>
```

Failure: `badarg` if the argument is not an atom.

error_handler (Module)

The error handler module defines what happens when certain types of errors occur.

Exports

```
undefined_function(Module, Func, ArgList) -> term()
```

Types:

- Module = Func = atom()
- ArgList = [term()]

This function is evaluated if a call is made to `Module:Func(ArgList)` which is undefined. This function is evaluated inside the process making the original call.

If `Module` is interpreted, the interpreter is invoked and the return value of the interpreted `Func(ArgList)` call is returned.

Otherwise, it returns, if possible, the value of `apply(Module, Func, ArgList)` after an attempt has been made to autoload `Module`. If this is not possible, the function calling `Module:Func(ArgList)` is exited.

```
undefined_lambda(Module, Fun, ArgList) -> term()
```

Types:

- Module = Fun = atom()
- ArgList = [term()]

This function is evaluated if a call is made to `Fun(ArgList)` when the module defining the `fun` is not loaded. This function is evaluated inside the process making the original call.

If `Module` is interpreted, the interpreter is invoked and the return value of the interpreted `Fun(ArgList)` call is returned.

Otherwise, it returns, if possible, the value of `apply(Fun, ArgList)` after an attempt has been made to autoload `Module`. If this is not possible, the process calling the `fun` is exited.

Notes

The code in `error_handler` is complex and should not be changed without fully understanding the interaction between the error handler, the `init` process of the code server, and the I/O mechanism of the code.

Changes in the code which may seem small can cause a deadlock as unforeseen consequences may occur. The use of `input` is dangerous in this type of code.

error_logger (Module)

The error logger is an event manager behaviour which runs with the registered name `error_logger` (see more about event managers/handlers in the Erlang Development Environment User's Guide and in `gen_event(3)`). All error messages from the Erlang runtime system are sent to this process as messages with the format `{emulator, Gleader, Str}`, where `Str` is a string which describes the error in plain English. The `Gleader` argument is the group leader process of the process causing the error. This is useful in a distributed setting as all error messages can be returned to the `error_logger` process on the originating node.

All errors detected by the standard libraries are reported with the `error_logger` functions. Errors detected in application modules should also be reported through the `error_logger` in order to get uniform reports.

Associated event handlers can be used to add private types of reports to the `error_logger`. An event handler which recognizes the specialized report type is first added to the `error_logger` (`add_report_handler/1,2`)

The standard configuration of the `error_logger` supports the logging of errors to the `tty`, or to a specified `file`. There is also a multi-file logger which logs all events, not only the standard error events, to several files. (see `log_mf_h(3)`).

All error events are tagged with the group leader `Gleader` in order to send the error to the originating node.

Exports

```
start() -> {ok, Pid} | {error, What}
start_link() -> {ok, Pid} | {error, What}
```

Types:

- `Pid` = `pid()`
- `What` = `{already_started, Pid}` | `term()`

Starts the `error_logger`. The `start_link` function should be used when the `error_logger` is supervised

```
error_report(Report) -> ok
```

Types:

- `Report` = `[{Tag, Data}]` | `[term()]` | `string()` | `term()`
- `Tag` = `term()`
- `Data` = `term()`

Sends a standard error report event to the error logger. This report event is handled by the standard event handler. The report is formatted as follows:

```
Tag1: Data1
Tag2: Data2
Term1
Term2
```

If Report is a string(), the string is written.

The report is written with an error heading.

```
error_report(Type,Report) -> ok
```

Types:

- Type = term()
- Report = [{Tag, Data}] | [term()] | string() | term()
- Tag = term()
- Data = term()

Sends a user defined error report type event to the error logger. If specialized error handling is required, an event handler recognizing this Type of report must first be added to the error_logger.

It is recommended that the Report follows the same structure as `error_report/1` above.

```
info_report(Report) -> ok
```

Types:

- Report = [{Tag, Data}] | [term()] | string() | term()
- Tag = term()
- Data = term()

Sends an information report to the error logger. This report event is handled by the standard event handler. The report is formatted as follows:

```
Tag1: Data1
Tag2: Data2
Term1
Term2
```

If Report is a string(), the string is written.

The report is written with an information heading.

```
info_report(Type,Report) -> ok
```

Types:

- Type = term()
- Report = [{Tag, Data}] | [term()] | string() | term()
- Tag = term()
- Data = term()

Sends a user defined information report type event to the error logger. If specialized error handling is required, an event handler recognizing this Type of report must first be added to the `error_logger`.

It is recommended that the Report follows the same structure as `info_report/1` above.

```
error_msg(Format) -> ok
error_msg(Format,Args) -> ok
format(Format,Args) -> ok
```

Types:

- Format = `string()`
- Args = `[term()]`

Sends an error event to the error logger. The `Format` and `Args` arguments are the same as the arguments of `io:format/2`. These events are handled by the standard event handler.

```
info_msg(Format) -> ok
info_msg(Format,Args) -> ok
```

Types:

- Format = `string()`
- Args = `[term()]`

Sends an information event to the error logger. The `Format` and `Args` arguments are the same as the arguments of `io:format/2`. These events are handled by the standard event handler.

```
tty(Flag) -> ok
```

Types:

- Flag = `true` | `false`

Enables or disables error printouts to the tty. If `Flag` is `false`, all text that the error logger would have sent to the terminal is discarded. If `Flag` is `true`, error messages are sent to the terminal screen.

```
logfile(Request) -> ok | FileName | {error, What}
```

Types:

- Request = `{open, FileName}` | `close` | `filename`
- FileName = `atom()` | `string()`
- What = `term()`

This function makes it possible to append a copy of all standard error printouts to a file. It can be used in combination with the `tty(false)` function in to have a silent system, where all errors are logged to a file.

Request can be:

- `{open, Filename}`. Opens the file `Filename` to store a copy of all error messages. Returns `ok`, or `{error, What}`.
- `close`. Closes the current log file. Returns `ok`, or `{error, What}`.

- `filename`. Returns `{error, What}` or `FileName`, where `FileName` is the name of the open log file.

There can only be one active log file.

```
add_report_handler(Module) -> ok | Other
add_report_handler(Module,Args) -> ok | Other
```

Types:

- `Module` = `atom()`
- `Args` = `term()`
- `Other` = `term()`

Adds a new event handler to the error logger. The event handler is initialized by a call to the `Module:init/1` function. This function must return `{ok, State}`. If anything else (`Other`) is returned, the handler is not added.

The report (event) handler will be called for every error event that the error logger receives (`Module:handle_event/2`). Errors dedicated to this handler should be handled accordingly.

```
delete_report_handler(Module) -> Return | {error, What}
```

Types:

- `Module` = `atom()`
- `Return` = `term()`
- `What` = `term()`

Deletes an error report (event) handler. The `Module:terminate/2` function is called in order to finalize the event handler. The return value of the `terminate/2` function is `Return`.

```
swap_handler(ToHandler) -> ok
```

Types:

- `ToHandler` = `tty` | `{logfile, File}`
- `File` = `atom()` | `string()`

The `error_logger` event manager is initially started with a primitive event handler which buffers and prints the raw error events. However, this function does install the standard event handler to be used according to the system configuration.

Events

The error logger event manager forwards the following events to all added event handlers. In the events that follow, Gleader is the group leader process identity of the error reporting process, and EPid is the process identity of the `error_logger`. All other variables are described with the function in which they appear.

{`error_report`, Gleader, {Epid, std_error, Report}} This event is generated when the `error_report/1` function is called.

{`error_report`, Gleader, {Epid, Type, Report}} This event is generated when the `error_report/2` function is called.

{`info_report`, Gleader, {Epid, std_info, Report}} This event is generated when the `info_report/1` function is called.

{`info_report`, Gleader, {Epid, Type, Report}} This event is generated when the `info_report/2` function is called.

{`error`, Gleader, {EPid, Format, Args}} This event is generated when the `error_msg` or `format` functions are called.

{`info_msg`, Gleader, {EPid, Format, Args}} This event is generated when the `info_msg` functions are called.

{`info`, Gleader, {EPid, term(), []}} This structure is only used by the `init` process for erroneously received messages.

{`emulator`, Gleader, string()} This event is generated by the runtime system. If the error was not issued by a special process, Gleader is `noproc`. This event should be handled in the `handle_info/2` function of the event handler.

Note:

All events issued by a process which has the group leader Gleader process located on another node will be passed to this node by the `error_logger`.

See Also

`gen_event(3)`, `log_mf_h(3)`

file (Module)

The module `file` provides an interface to the file system.

Most functions have a name argument such as a file name or directory name, which is either an atom, a string, or a deep list of characters and atoms. A path is a list of directory names. If the functions are successful, they return `ok`, or `{ok, Value}`.

If an error occurs, the return value has the format `{error, Reason}`. Reason is an atom which is named from the Posix error codes used in Unix, and in the runtime libraries of most C compilers. In the following descriptions of functions, the most typical error codes are listed. By matching the error code, applications can use this information for error recovery. To produce a readable error string, use `format_error/1`.

Exports

`change_group(Filename, Gid)`

Change group of a file. See `write_file_info/2`.

`change_owner(Filename, Uid)`

Change owner of a file. See `write_file_info/2`.

`change_owner(Filename, Uid, Gid)`

Change owner and group of a file. See `write_file_info/2`.

`change_time(Filename, Mtime)`

Change the modification and access times of a file. See `write_file_info/2`.

`change_time(Filename, Mtime, Atime)`

Change the modification and access times of a file. See `write_file_info/2`.

`close(IoDevice)`

Closes the file referenced by `IoDevice`. It returns `ok`.

`consult(Filename)`

Opens file `Filename` and reads all the Erlang terms in it. Returns one of the following:

`{ok, TermList}` The file was successfully read.

{error, Atom} An error occurred when opening the file or reading it. The Atom is a Posix error code. See the description of open/2 for a list of typical error codes.
{error, {Line, Mod, Term}} An error occurred when interpreting the Erlang terms in the file. Use the format_error/1 function to convert the three-element tuple to an English description of the error.

del_dir(DirName)

Tries to delete the directory DirName. The directory must be empty before it can be deleted. Returns ok if successful.

Typical error reasons are:

eacces Missing search or write permissions for the parent directories of DirName.
eexist The directory is not empty.
enoent The directory does not exist.
enotdir A component of DirName is not a directory. On some platforms, enoent is returned instead.
einval Attempt to delete the current directory. On some platforms, eacces is returned instead.

delete(Filename)

Tries to delete the file Filename. Returns ok if successful.

Typical error reasons are:

enoent The file does not exist.
eacces Missing permission for the file or one of its parents.
eperm The file is a directory and the user is not super-user.
enotdir A component of the file name is not a directory. On some platforms, enoent is returned instead.

eval(Filename)

Opens the file Filename and evaluates all the expression sequences in it. It returns one of the following:

ok The file was read and evaluated. The actual result of the evaluation is not returned; any expression sequence in the file must be there for its side effect.
{error, Atom} An error occurred when opening the file or reading it. The Atom is a Posix error code. See the description of open/2 for a list of typical error codes.
{error, {Line, Mod, Term}} An error occurred when interpreting the Erlang terms in the file. Use the format_error/1 function to convert the three-element tuple to an English description of the error.

file_info(Filename)

Note:

This function is obsolete. Use `read_file_info` instead.

Retrieves information about a file. Returns `{ok, FileInfo}` if successful, otherwise `{error, Reason}`. `FileInfo` is a tuple with the following fields:

`{Size, Type, Access, AccessTime, ModifyTime, UnUsed1, UnUsed2}`

`Size` The size of the file in bytes.

`Type` The type of file which is `device`, `directory`, `regular`, or `other`.

`Access` The current system access to the file, which is one of the atoms `read`, `write`, `read_write`, or `none`.

`AccessTime` The last time the file was read, shown in the format `{Year, Month, Day, Hour, Minute, Second}`.

`ModifyTime` The last time the file was written, shown in the format `{Year, Month, Day, Hour, Minute, Second}`.

`UnUsed1`, `UnUsed2` These fields are not used, but reserved for future expansion. They probably contain unused.

Typical error reasons: Same as for `read_file_info/1`.

`format_error(ErrorDescriptor)`

Given the error reason returned by any function in this module, it returns a descriptive string of the error in English.

`get_cwd()`

Returns `{ok, CurDir}`, where `CurDir` (a string) is the current working directory of the file server.

Note:

In rare circumstances, this function can fail on Unix. It may happen if read permission does not exist for the parent directories of the current directory.

Typical error reasons are:

`eacces` Missing read permission for one of the parents of the current directory.

`get_cwd(Drive)`

Drive should be of the form "Letter:", for example "c:". Returns `{ok, CurDir}` or `{error, Reason}`, where `CurDir` (a string) is the current working directory of the drive specified.

This function returns `{error, enotsup}` on platforms which have no concept of current drive (Unix, for example).

Typical error reasons are:

enotsup The operating system have no concept of drives.
eacces The drive does not exist.
EINVAL The format of Drive is invalid.

list_dir(DirName)

Lists all the files in a directory. Returns {ok, FilenameList} if successful. Otherwise, it returns {error, Reason}. FilenameList is a list of the names of all the files in the directory. Each name is a string. The names are not sorted.

Typical error reasons are:

eacces Missing search or write permissions for DirName or one of its parent directories.
ENOENT The directory does not exist.

make_dir(DirName)

Tries to create the directory DirName. Missing parent directories are NOT created. Returns ok if successful.

Typical error reasons are:

eacces Missing search or write permissions for the parent directories of DirName.
EEXIST There is already a file or directory named DirName.
ENOENT A component of DirName does not exist.
ENOSPC There is a no space left on the device.
ENOTDIR A component of DirName is not a directory. On some platforms, ENOENT is returned instead.

make_link(Existing, New)

Makes a hard link from Existing to New, on platforms that support links (Unix). This function returns ok if the link was successfully created, or {error,Reason}. On platforms that do not support links, {error,enotsup} will be returned.

Typical error reasons:

eacces Missing read or write permissions for the parent directories of Existing or New.
EEXIST new already exists.
ENOTSUP Hard links are not supported on this platform.

make_symlink(Name1, Name2)

This function creates a symbolic link Name2 to the file or directory Name1, on platforms that support symbolic links (most Unix systems). Name1 need not exist. This function returns ok if the link was successfully created, or {error,Reason}. On platforms that do not support symbolic links, {error,enotsup} will be returned.

Typical error reasons:

eacces Missing read or write permissions for the parent directories of Existing or New.
EEXIST new already exists.

enotsup Symbolic links are not supported on this platform.

open(Filename, ModeList)

Opens the file `Filename` in the mode determined by `ModeList`. `ModeList` may contain one or more of the following items:

`read` The file, which must exist, is opened for reading.

`write` The file is opened for writing. It is created if it does not exist. Otherwise, it is truncated (unless combined with `read`).

`append` The file will be opened for writing, and it will be created if it does not exist. Every write operation to a file opened with `append` will take place at the end of the file.

`raw` The `raw` option allows faster access to a file, because no Erlang process is needed to handle the file. However, a file opened in this way has the following limitations:

- The functions in the `io` module cannot be used, because they can only talk to an Erlang process. Instead, use the `read/2` and `write/2` functions.
- Only the Erlang process which opened the file can use it.
- A remote Erlang file server cannot be used; the computer on which the Erlang node is running must have access to the file system (directly or through NFS).

`binary` This option can only be used if the `raw` option is specified as well. When specified, read operations on the file using the `read/2` function will return binaries rather than lists.

If both `read` and `write` are specified, the file is created if it does not exist. It is not truncated if it exists.

Returns:

{`ok`, `IODevice`} The file has been opened in the requested mode. `IODevice` is a reference to the file.

{`error`, `Reason`} The file could not be opened.

A `file descriptor` is the Pid of the process which handles the file. The file process is linked to the process which originally opened the file. If any process to which the file process is linked terminates, the file will be closed by the file process and the process itself will be terminated. The file descriptor returned from this call can be used as an argument to the I/O functions (see `io`).

Note:

In previous versions of `file`, modes were given as one of the atoms `read`, `write`, or `read_write` instead of a list. This is still allowed for reasons of backwards compatibility, but should not be used for new code. Also note that `read_write` is not allowed in a mode list.

Typical error reasons:

`enoent` The file does not exist.

`eacces` Missing permission for reading the file or searching one of the parent directories.

`eisdir` The named file is a directory.

enotdir A component of the file name is not a directory. On some platforms, `enoent` is returned instead.

enospc There is no space left on the device (if `write` access was specified).

`path_consult(Path, Filename)`

Searches the path `Path` (a list of directory names) until the file `Filename` is found. If `Filename` is an absolute file name, `Path` is ignored. The file is opened and all the terms in it are read. The function returns one of the following:

{`ok`, `TermList`, `FullName`} The file was successfully read. `FullName` is the full name of the file which was opened and read.

{`error`, `enoent`} The file could not be found in any of the directories in `Path`.

{`error`, `Atom`} An error occurred when opening the file or reading it. The `Atom` is a Posix error code. See the description of `open/2` for a list of typical error codes.

{`error`, {`Line`, `Mod`, `Term`}} An error occurred when interpreting the Erlang terms in the file. Use the `format_error/1` function to convert the three-element tuple to an English description of the error.

`path_eval(Path, Filename)`

Searches the path `Path` (a list of directory names) until the file `Filename` is found. If `Filename` is an absolute file name, `Path` is ignored. The file is opened and all the expression sequences in it are evaluated. The function returns one of the following:

{`ok`, `FullName`} The file was read. `FullName` is the full name of the file which was opened and evaluated.

{`error`, `enoent`} The file could not be found in any of the directories in `Path`.

{`error`, `Atom`} An error occurred when opening the file or reading it. The `Atom` is a Posix error code. See the description of `open/2` for a list of typical error codes.

{`error`, {`Line`, `Mod`, `Term`}} An error occurred when interpreting the Erlang terms in the file. Use the `format_error/1` function to convert the three-element tuple to an English description of the error.

`path_open(Path, Filename, Mode)`

Searches the path `Path` (a list of directory names) until the file `Filename` is found. If `Filename` is an absolute file name, `Path` is ignored. The function returns one of the following:

{`ok`, `IODevice`, `FullName`} The file was opened in the requested mode. `IODevice` is a reference to the file and `FullName` is the full name of the file which was opened.

{`error`, `enoent`} `Filename` was not found in the path.

{`error`, `Reason`} There was an error opening `Filename`.

`position(IODevice, Location)`

Sets the position of the file referenced by `IODevice` to `Location`. Returns {`ok`, `NewPosition`} (as absolute offset) if successful, otherwise {`error`, `Reason`}. `Location` is one of the following:

```
{bof, Offset} Absolute offset  
{cur, Offset} Offset from the current position  
{eof, Offset} Offset from the end of file  
Integer The same as {bog, Integer}  
bog || cur || eof The same as above with Offset 0.
```

Typical error reasons are:

EINVAL Either the Location was illegal, or it evaluated to a negative offset in the file.
Note that if the resulting position is a negative value you will get an error but after the call it is undefined where the file position will be.

pread(IoDevice, Location, Number)

Combines position/2 and read/2 in one operation, which is more efficient than calling them one at a time. If IoDevice has been opened in raw mode, some restrictions apply: Location is only allowed to be an integer; and the current position of the file is undefined after the operation.

pwrite(IoDevice, Location, Bytes)

Combines position/2 and write/2 in one operation, which is more efficient than calling them one at a time. If IoDevice has been opened in raw mode, some restrictions apply: Location is only allowed to be an integer; and the current position of the file is undefined after the operation.

read(IoDevice, Number)

Reads Number bytes from the file described by IoDevice. This function is the only way to read from a file opened in raw mode (although it works for normally opened files, too). Returns:

{ok, ListOrBinary} If the file was opened in binary mode, the read bytes are returned in a binary, otherwise in a list. The list or binary will be shorter than the the number of bytes requested if the end of the file is reached.
EOF EOF is returned if the Number was greater than zero and end of file was reached before anything at all could be read.
{error, Reason} A Posix error code will be returned if an error occurred.

Typical error reasons:

EBADF The file is not opened for reading.

read_file(Filename)

Returns {ok, Binary}, where Binary is a binary data object that contains the contents of Filename, or {error, Reason} if an error occurs.

Typical error reasons:

ENOENT The file does not exist.

EACCES Missing permission for reading the file, or for searching one of the parent directories.

eisdir The named file is a directory.

enotdir A component of the file name is not a directory. On some platforms, **enoent** is returned instead.

ENOMEM There is not enough memory for the contents of the file.

read_file_info(Filename)

Retrieves information about a file. Returns `{ok, FileInfo}` if successful, otherwise `{error, Reason}`. `FileInfo` is a record. Its definition can be found by including `file.hrl` from the kernel application:

```
-include_lib("kernel/include/file.hrl").
```

The record contains the following fields.

size Size of file in bytes.

type The type of the file which can be `device`, `directory`, `regular`, or `other`.

access The current system access to the file, which is one of the atoms `read`, `write`, `read_write`, or `none`.

atime The last (local) time the file was read, in the format `{Year, Month, Day}, {Hour, Minute, Second}`.

mtime The last (local) time the file was written, in the format `{Year, Month, Day}, {Hour, Minute, Second}`.

ctime The interpretation of this time field depends on the operating system. On Unix, it is the last time the file or or the inode was changed. In Windows, it is the create time. The format is `{Year, Month, Day}, {Hour, Minute, Second}`.

mode An integer which gives the file permissions as a sum of the following bit values:

8#00400 read permission: owner

8#00200 write permission: owner

8#00100 execute permission: owner

8#00040 read permission: group

8#00020 write permission: group

8#00010 execute permission: group

8#00004 read permission: other

8#00002 write permission: other

8#00001 execute permission: other

16#800 set user id on execution

16#400 set group id on execution

On Unix platforms, other bits than those listed above may be set.

links Number of links to the file (this will always be 1 for file systems which have no concept of links).

major_device An integer which identifies the file system where the file is located. In Windows, the number indicates a drive as follows: 0 means A:, 1 means B:, and so on.

minor_device Only valid for character devices on Unix. In all other cases, this field is zero.

inode An integer which gives the `inode` number. On non-Unix file systems, this field will be zero.

- uid An integer which indicates the owner of the file. Will be zero for non-Unix file systems.
- gid An integer which gives the group that the owner of the file belongs to. Will be zero for non-Unix file systems.

Typical error reasons:

- `eacces` Missing search permission for one of the parent directories of the file.
- `enoent` The file does not exist.
- `enotdir` A component of the file name is not a directory. On some platforms, `enoent` is returned instead.

`read_link(Linkname)`

This function returns `{ok,Filename}` if `Linkname` refers to a symbolic link or `{error,Reason}` otherwise. On platforms that do not support symbolic links, the return value will be `{error,enotsup}`.

Typical error reasons:

- `einval` `Linkname` does not refer to a symbolic link.
- `enoent` The file does not exist.
- `enotsup` Symbolic links are not supported on this platform.

`read_link_info(Filename)`

This function works like `read_file_info/1`, except that if `Filename` is a symbolic link, information about the link will be returned in the `file_info` record and the type field of the record will be set to `symlink`. If `Filename` is not a symbolic link, this function returns exactly the same result as `read_file_info/1`. On platforms that do not support symbolic link, this function is always equivalent to `read_file_info/1`.

`rename(Source, Destination)`

Tries to rename the file `Source` to `Destination`. It can be used to move files (and directories) between directories, but it is not sufficient to specify the destination only. The destination file name must also be specified. For example, if `bar` is a normal file and `foo` and `baz` are directories, `rename("foo/bar", "baz")` returns an error, but `rename("foo/bar", "baz/bar")` succeeds. Returns `ok` if it is successful.

Note:

Renaming of open files is not allowed on most platforms (see `eacces` below).

Typical error reasons:

- `eacces` Missing read or write permissions for the parent directories of `Source` or `Destination`. On some platforms, this error is given if either `Source` or `Destination` is open.
- `eexist` `Destination` is not an empty directory. On some platforms, also given when `Source` and `Destination` are not of the same type.

einval Source is a root directory, or Destination is a sub-directory of Source.
eisdir Destination is a directory, but Source is not.
enoent Source does not exist.
enotdir Source is a directory, but Destination is not.
exdev Source and Destination are on different file systems.

set_cwd(DirName)

Sets the current working directory of the file server to DirName. Returns ok if successful.
 Typical error reasons are:

enoent The directory does not exist.
enotdir A component of DirName is not a directory. On some platforms, enoent is returned.
eacces Missing permission for the directory or one of its parents.

sync(IoDevice)

Makes sure that any buffers kept by the operating system (not by the Erlang system) are written to disk. On some platforms, this function might have no effect .

truncate(IoDevice)

Truncates the file referenced by IoDevice at the current position. Returns ok if successful, otherwise {error, Reason}.

write(IoDevice, Bytes)

Writes Bytes (possibly a deep list of characters, or a binary) to the file described by IoDevice. This function is the only way to write to a file opened in raw mode (although it works for normally opened files, too).

This function returns ok if successful, and {error, Reason} otherwise.

Typical error reasons are:

ebadf The file is not opened for writing.
enospc There is a no space left on the device.

write_file(Filename, Binary)

Writes the contents of the binary data object Binary to the file Filename. The file is created if it does not exist already. If it exists, the previous contents are overwritten. Returns ok, or {error, Reason}.

Typical error reasons are:

enoent A component of the file name does not exist.
enotdir A component of the file name is not a directory. On some platforms, enoent is returned instead.
enospc There is a no space left on the device.
eacces Missing permission for writing the file or searching one of the parent directories.

eisdir The named file is a directory.

write_file_info(Filename, FileInfo)

Change file information. Returns `ok` if successful, otherwise `{error, Reason}`.

`FileInfo` is a record. Its definition can be found by including `file.hrl` from the kernel application:

```
-include_lib("kernel/include/file.hrl").
```

The following fields are used from the record if they are given.

`atime` The last (local) time the file was read, in the format `{Year, Month, Day}, {Hour, Minute, Second}`.

`mtime` The last (local) time the file was written, in the format `{Year, Month, Day}, {Hour, Minute, Second}`.

`ctime` On Unix, any value give for this field will be ignored (the “`ctime`” for the file will be set to the current time). On Windows, this field is the new creation time to set for the file. The format is `{Year, Month, Day}, {Hour, Minute, Second}`.

`mode` An integer which gives the file permissions as a sum of the following bit values:

8#00400 read permission: owner

8#00200 write permission: owner

8#00100 execute permission: owner

8#00040 read permission: group

8#00020 write permission: group

8#00010 execute permission: group

8#00004 read permission: other

8#00002 write permission: other

8#00001 execute permission: other

16#800 set user id on execution

16#400 set group id on execution

On Unix platforms, other bits than those listed above may be set.

`uid` An integer which indicates the owner of the file. Ignored for non-Unix file systems.

`gid` An integer which gives the group that the owner of the file belongs to. Ignored non-Unix file systems.

Typical error reasons:

`eacces` Missing search permission for one of the parent directories of the file.

`enoent` The file does not exist.

`enotdir` A component of the file name is not a directory. On some platforms, `enoent` is returned instead.

POSIX Error Codes

eacces permission denied
eagain resource temporarily unavailable
ebadf bad file number
ebusy file busy
edquot disk quota exceeded
eexist file already exists
efault bad address in system call argument
efbig file too large
eintr interrupted system call
EINVAL invalid argument
eio I/O error
eisdir illegal operation on a directory
eloop too many levels of symbolic links
emfile too many open files
mlink too many links
enametoolong file name too long
enfile file table overflow
enodev no such device
enoent no such file or directory
ENOMEM not enough memory
enospc no space left on device
enotblk block device required
enotdir not a directory
enotsup operation not supported
enxio no such device or address
eperm not owner
epipe broken pipe
erofs read-only file system
espipe invalid seek
esrch no such process
estale stale remote file handle
exdev cross-domain link

Warnings

If an error occurs when accessing an open file with the `io` module, the process which handles the file will exit. The dead file process might hang if a process tries to access it later. This will be fixed in a future release.

See Also

[filename\(3\)](#)

gen_tcp (Module)

The `gen_tcp` module provides functions for communicating with sockets using the TCP/IP protocol.

The available options are described in the `setopts/2` [page 133] function in the `inet` manual page.

The possible `{error, Reason}` results are described in the `inet` [page 134] manual page.

The following code fragment provides a simple example of a client connecting to a server at port 5678, transferring a binary and closing the connection.

```
client() ->
    SomeHostInNet = "localhost" % to make it runnable on one machine
    {ok, Sock} = gen_tcp:connect(SomeHostInNet, 5678,
                                 [binary, {packet, 0}]),
    ok = gen_tcp:send(Sock, "Some Data"),
    ok = gen_tcp:close(Sock).
```

At the other end a server is listening on port 5678, accepts the connection and receives the binary.

```
server() ->
    {ok, LSock} = gen_tcp:listen(5678, [binary, {packet, 0},
                                         {active, false}]),
    {ok, Sock} = gen_tcp:accept(LSock),
    {ok, Bin} = do_recv(Sock, []),
    ok = gen_tcp:close(Sock),
    Bin.

do_recv(Sock, Bs) ->
    case gen_tcp:recv(Sock, 0) of
        {ok, B} ->
            do_recv(Sock, [Bs, B]);
        {error, closed} ->
            {ok, list_to_binary(Bs)}
    end.
```

Exports

```
accept(ListenSocket) -> {ok, Socket} | {error, Reason}
accept(ListenSocket, Timeout) -> {ok, Socket} | {error, Reason}
```

Types:

- ListenSocket = socket()
- Socket = socket()
- Timeout = integer()
- Reason = atom()

Accepts an incoming connection request on a listen socket. Socket must be a socket returned from `listen/1`. If no `Timeout` argument is specified, or it is `infinity`, the `accept` function will not return until a connection has been established or the `ListenSocket` has been closed. If `accept` returns because the `ListenSocket` has been closed `{error, closed}` is returned. If `Timeout` is specified and no connection is accepted within the given time, `accept` will return `{error, timeout}`.

Packets can be sent to the returned socket using the `send/2` function. Packets sent from the peer will be delivered as messages

```
{tcp, Socket, Data}
```

unless `{active, false}` was specified in the option list for the listen socket, in which case packets should be retrieved by calling `recv/2`.

```
close(Socket) -> ok | {error, Reason}
```

Types:

- Socket = socket()
- Reason = atom()

Closes an TCP socket.

```
connect(Address, Port, Options) -> {ok, Socket} | {error, Reason}
connect(Address, Port, Options, Timeout) -> {ok, Socket} | {error, Reason}
```

Types:

- Address = string() | atom() | ip_address()
- Port = Timeout = integer()
- Options = list()
- Socket = socket()
- Reason = atom()

Connects to a server on TCP port `Port` on the host with IP address `Address`. The `Address` argument can be either a hostname, or an IP address.

The available options are:

`list` Received Packet is delivered as a list.

`binary` Received Packet is delivered as a binary.

common inet options The common `inet` options available are described in the `setopts/2` [page 133] function in the `inet` manual page.

Packets can be sent to the returned socket using the `send/2` function. Packets sent from the peer will be delivered as messages

```
{tcp, Socket, Data}
```

If the socket was closed the following message is delivered:

```
{tcp_closed, Socket}
```

If an error occurred on the socket the following message is delivered:

```
{tcp_error, Socket, Reason}
```

unless the socket is in passive mode, in which case packets are retrieved by calling `recv/2`.

The optional `Timeout` parameter specifies a timeout in milliseconds. The default value is `infinity`.

```
controlling_process(Socket, NewOwner) -> ok | {error, eperm}
```

Types:

- `Socket` = `socket()`
- `NewOwner` = `pid()`

Assigns a new controlling process to `Socket`. The controlling process is the process which will receive messages from the socket. If called by any other process than the current owner `{error, eperm}` will be returned.

```
listen(Port, Options) -> {ok, Socket} | {error, Reason}
```

Types:

- `Port` = `integer()`
- `Options` = `list()`
- `Socket` = `socket()`
- `Reason` = `atom()`

Sets up socket to listen on the port `Port` on the local host.

If the port number is zero, the `listen` function picks an available port number (use `inet:port/1` to retrieve it); otherwise, the specified port number is used.

The available options are described in the `setopts/2` [page 133] function in the `inet` manual page. Additionally, the option `{backlog, B}` can be given, where `B` is an integer ≥ 0 . The backlog value defaults to 5. The backlog value defines the maximum length the queue of pending connections may grow to.

The returned socket can only be used in calls to `accept`.

```
recv(Socket, Length) -> {ok, Packet} | {error, Reason}
```

```
recv(Socket, Length, Timeout)
```

Types:

- `Socket` = `socket()`
- `Length` = `integer()`
- `Packet` = `list() | binary()`

- Timeout = integer()
- Reason = atom()

This function receives a packet from a socket in passive mode. A closed socket is indicated by a return value of {error, closed}.

The Length argument is only meaningful when the socket is in raw mode and denotes number of bytes to read. If Length = 0 all available bytes are returned.

The optional Timeout parameter specifies a timeout in milliseconds. The default value is infinity.

```
send(Socket, Packet) -> ok | {error, Reason}
```

Types:

- Socket = socket()
- Packet = list() | binary()
- Reason = atom()

Sends a packet on a socket.

gen_udp (Module)

The `gen_udp` module is an interface to User Datagram Protocol (UDP).

The possible `{error, Reason}` results are described in the `inet` [page 134] manual page.

Exports

`close(Socket) -> ok | {error, Reason}`

Types:

- `Socket = Reason = term()`

Removes the `Socket` created with `open/1` or `open/2`.

`controlling_process(Socket, NewOwner) ->`

Types:

- `Socket = term()`
- `NewOwner = pid()`

The process associated with a `Socket` is changed to `NewOwner`. The `NewOwner` will receive all subsequent data.

`open(Port) -> {ok, Socket} | {error, Reason}`

`open(Port, Options) -> {ok, Socket} | {error, Reason}`

Types:

- `Port = integer(0..65535)`
- `Options = list()`
- `Socket = term()`
- `Reason = term()`

Associates a UDP port number (`Port`) with the calling process. It returns `{ok, Socket}`, or `{error, Reason}`. The returned `Socket` is used to send packets from this port with the `send/4` function. `Options` is a list of options associated with this port.

When UDP packets arrive at the opened `Port` they will be delivered as messages of the type `{udp, Socket, IP, InPortNo, Packet}`

`IP` and `InPortNo` define the address from which `Packet` came. `Packet` is a list of bytes if the option `list` was specified. `Packet` is a binary if the option `binary` was specified.

The available options are:

`list` Received `Packet` is delivered as a list.

binary Received Packet is delivered as a binary.

common inet options The common inet options available are described in the `setopts/2` [page 133] function in the `inet` manual page.

If you set Port to 0, the underlying Operating System assigns a free UDP port. (You can find out which port by calling `inet:port(Socket)`.)

If any of the following functions are called with a Socket that was not opened by the calling process, they will return `{error,not_owner}`. The ownership of a Socket can be transferred to another process with `controlling_process/2`.

```
recv(Socket, Length) -> {ok,{Address, Port, Packet}} | {error, Reason}
recv(Socket, Length, Timeout)
```

Types:

- `Socket` = `socket()`
- `Address` = `{ integer(), integer(), integer(), integer() }`
- `Port` = `integer(0..65535)`
- `Length` = `integer()`
- `Packet` = `list() | binary()`
- `Timeout` = `integer()`
- `Reason` = `atom()`

This function receives a packet from a socket in passive mode.

The optional `Timeout` parameter specifies a timeout in milliseconds. The default value is infinity.

```
send(S,Address,Port,Packet) -> ok | {error, Reason}
```

Types:

- `Address` = `{ integer(), integer(), integer(), integer() } | atom() | string()`
- `Port` = `integer(0..65535)`
- `Packet` = `[byte()] | binary()`
- `Reason` = `term()`

Sends `Packet` to the specified address (address, port). It returns `ok`, or `{error, Reason}`. `Address` can be an IP address expressed as a tuple, for example `{192, 0, 0, 1}`. It can also be a host name expressed as an atom or a string, for example `'somehost.some.domain'`. `Port` is an integer, and `Packet` is either a list of bytes or a binary.

global (Module)

This documentation describes the Global module which consists of the following functionalities:

1. Registration of global names
2. Global locks
3. Monitoring nodes
4. Maintenance of the fully connected network

These services are controlled via the process `global` which exists on every node. `global` is started automatically when a node is started.

The ability to globally register names is a central concept in the programming of distributed Erlang systems. In this module, the equivalent of the `register/2` and `whereis/1` BIFs are implemented, but for a network of Erlang nodes. A registered name is an alias for a process identity `Pid`. The system monitors globally registered Pids. If a process terminates, the name will also be globally unregistered.

The registered names are stored in replica global name tables on every node. There is no central storage point. Thus, the translation of a name to a `Pid` is extremely quick because it is never a network operation. When any action is taken which results in a change to the global name table all tables on other nodes are automatically updated.

Global locks have lock identities and are set on a specific resource. For instance, the specified resource could be a `Pid` of a process. When a global lock is set access to the locked resource is denied for all other resources other than the lock requester.

Both the registration and lock functionalities are atomic. All nodes involved in these actions will have the same view of the information.

The server also performs the critical task of continuously monitoring changes in node configuration, if a node which runs a globally registered process goes down, the name will be globally unregistered. The server will also maintain a fully connected network. For example, if node `N1` connects to node `N2` (which is already connected to `N3`), the `global` server on `N1` then `N3` will make sure that also `N1` and `N3` are connected. If this is not desired, the command line flag `-connect_all false` must be passed to `init` at boot time. In this case, the name registration facility cannot be used (but the lock mechanism will still work.)

Exports

```
del_lock(Id)
del_lock(Id, Nodes) -> void()

Types:
• Id = {ResourceId, LockRequesterId}
```

- ResourceId = term()
- LockRequesterId = term()
- Nodes = [node()]

Deletes the lock Id synchronously.

```
notify_all_name(Name, Pid1, Pid2) -> none
```

This function can be used as a name resolving function for `register_name/3` and `re_register_name/3`. It unregisters both Pids, and sends the message `{global_name_conflict, Name, OtherPid}` to both processes.

```
random_exit_name(Name, Pid1, Pid2) -> Pid1 | Pid2
```

This function can be used as a name resolving function for `register_name/3` and `re_register_name/3`. It randomly chooses one of the Pids for registration and kills the other one.

```
random_notify_name(Name, Pid1, Pid2) -> Pid1 | Pid2
```

This function can be used as a name resolving function for `register_name/3` and `re_register_name/3`. It randomly chooses one of the Pids for registration, and sends the message `{global_name_conflict, Name}` to the other Pid.

```
register_name(Name, Pid)
```

```
register_name(Name, Pid, Resolve) -> yes | no
```

Types:

- Name = term()
- Pid = Pid()
- Resolve = {M, F} where M:F(Name, Pid, Pid2) -> Pid | Pid2 | none

Globally notifies all nodes of a new global name in a network of Erlang nodes.

When new nodes are added to the network, they are informed of the globally registered names that already exist. The network is also informed of any global names in newly connected nodes. If any name clashes are discovered, the `Resolve` function is called. Its purpose is to decide which Pid is correct. This function blocks the global name server during its execution. If the function crashes, or returns anything other than one of the Pids, the name is unregistered. This function is called once for each name clash.

There are three pre-defined resolve functions, `random_exit_name`, `random_notify_name` and `notify_all_name`. If no `Resolve` function is defined, `random_exit_name` is used. This means that one of the two registered processes will be selected as correct while the other is killed.

This function is completely synchronous. This means that when this function returns, the name is either registered on all nodes or none.

The function returns `yes` if successful, `no` if it fails. For example, `no` is returned if an attempt is made to register a process with a name that is already in use.

If a process with a registered name dies, or the node goes down, the name is unregistered on all nodes.

```
registered_names() -> [Name]
```

Types:

- Name = term()

Returns a lists of all globally registered names.

```
re_register_name(Name, Pid)
re_register_name(Name, Pid, Resolve) -> void()
```

Types:

- Name = term()
- Pid = Pid()
- Resolve = {M, F} where M:F(Name, Pid, Pid2) -> Pid | Pid2 | none

Atomically changes the registered name `Name` on all nodes to refer to `Pid`.

The `Resolve` function has the same behavior as in `register_name`.

```
send(Name, Msg) -> Pid
```

Types:

- Name = term()
- Msg = term()
- Pid = Pid()

Sends the message `Msg` to the globally registered process `Name`. If `Name` is not a globally registered name, the calling function will exit with reason `{badarg, {Name, Msg}}`.

```
set_lock(Id)
set_lock(Id, Nodes)
set_lock(Id, Nodes, Retries) -> boolean()
```

Types:

- Id = {ResourceId, LockRequesterId}
- ResourceId = term()
- LockRequesterId = term()
- Nodes = [node()]
- Retries = int() > 0 | infinity

Sets a lock on the specified nodes (or on all nodes if none are specified) on `ResourceId` for `LockRequesterId`. If a lock already exists on `ResourceId` for another requester than `LockRequesterId`, and `Retries` is not equal to 0, the process sleeps for a while and will try to execute the action later. When `Retries` attempts have been made, `false` is returned, otherwise `true`. If `Retries` is `infinity`, `true` is eventually returned (unless the lock is never released).

If no value for `Retries` is given, `infinity` is used.

This function is completely synchronous.

If a process which holds a lock dies, or the node goes down, the locks held by the process are deleted.

`global` keeps track of all processes sharing the same lock, i.e. if two processes set the same lock both processes must delete the lock.

This function does not address the problem of a deadlock. A deadlock can never occur as long as processes only lock one resource at a time. But if some processes try to lock two or more resources, a deadlock may occur. It is up to the application to detect and rectify a deadlock.

```
start()  
start_link() -> {ok, Pid} | {error, Reason}
```

This function starts the global name server. Normally, the server is started automatically.

```
stop() -> void()
```

Stops the global name server.

```
sync() -> void()
```

Synchronizes the global name server with all nodes known to this node. These are the nodes which are returned from `erlang:nodes()`. When this function returns, the global name server will receive global information from all nodes. This function can be called when new nodes are added to the network.

```
trans(Id, Fun)  
trans(Id, Fun, Nodes)  
trans(Id, Fun, Nodes, Retries) -> Res | aborted
```

Types:

- `Id` = `{ResourceId, LockRequesterId}`
- `ResourceId` = `term()`
- `LockRequesterId` = `term()`
- `Fun` = `fun() | {M, F}`
- `Nodes` = `[node()]`
- `Retries` = `int() > 0 | infinity`
- `Res` = `term()`

Sets a lock on `Id` (using `set_lock/3`). Evaluates `Res` = `Fun()` if successfully locked and returns `Res`. Returns `aborted` if the lock attempt failed. If `Retries` is set to `infinity`, the transaction will not abort.

`infinity` is the default setting and will be used if no value is given for `Retries`.

```
unregister_name(Name) -> void()
```

Types:

- `Name` = `term()`

Globally removes `Name` from the network of Erlang nodes.

```
whereis_name(Name) -> Pid() | undefined
```

Types:

- `Name` = `term()`

Returns either an atom `undefined`, or a `Pid` which is globally associated with `Name`.

global_group (Module)

The global group function makes it possible to group the nodes in a system into partitions, each partition having its own global name space, refer to `global(3)`. These partitions are called global groups.

The main advantage of dividing systems to global groups is that the background load decreases while the number of nodes to be updated is reduced when manipulating globally registered names.

The `global_groups`-key in the `.config` file defines the global groups:

```
{global_groups, [{GroupName, [Node]}]}
```

`GroupName` is an `atom()` naming a global group.

`Node` is an `atom()` naming a node.

The command `erl -config File` starts a node with a configuration file named `File.config`. If the `global_groups`-key is not defined the system will start as a whole, without any partitions. When the key is not defined, the services of this function will not give any extra value to `global(3)`.

For the processes and nodes to run smoothly using this function the following criteria must be met:

- The global group function must have a server process, `global_group`, running on each node.
NOTE: The processes are automatically started and synchronized when a node is started.
- All processes must agree with the group definition in the immediate global group. If two nodes do not agree, these nodes will not synchronize their name space and an error message will be logged in the error logger.
Example: If one node has an illegal global group definition, such a node will run isolated from the other nodes regarding the global name space; but not regarding other system functions, e.g distribution of applications, refer to chapter NOTE below.
- Nodes can only belong to one global group.

When the global group definitions are to be changed in a system upgrade, the upgrade must fulfill the following steps:

1. First, all nodes which are to be removed from a global group must be taken down.
2. Nodes which are not affected by the redefinition of the global groups are to be upgraded to be aware of the new global group definitions.
NOTE: All nodes in the system, also nodes in unchanged global groups, must be upgraded. This because e.g `send` must have an accurate view of the total system.
3. Finally, all nodes which are new to a global group can be started.

When a non partitioned system is to be upgraded to become a partitioned system, all nodes belonging to a global group will be disconnected from all nodes not belonging to its immediate global group.

Exports

`global_groups() -> {OwnGroupName, [OtherGroupName]} | undefined`

Types:

- `OwnGroupName = atom()`
- `OtherGroupName = atom()`
- `ErrorMsg = term()`

Returns the names of all the global groups known to the immediate global group.

`info() -> [{state, State}, {own_group_name, atom()}, {own_group_nodes, [Node]}, {synced_nodes, [Node]}, {sync_error, [Node]}, {no_contact, [Node]}, {other_groups, Other_grps}, {monitoring, [pid()]}]`

Types:

- `State = no_conf | synced`
- `Other_grps = [{OtherGrpName, [Node]}]`
- `OtherGrpName = atom()`
- `Node = atom()`

Returns the state of the global group process. In the following 'nodes' refers to nodes in the immediate global group. `synced_nodes` lists the nodes this node is synchronized with at this moment. `own_group_nodes` lists the nodes defining the own global group. `sync_error` lists the nodes with this node could not be synchronize. `no_contact` lists nodes with this node do not yet have established contact. `other_groups` shows the definition of the other global groups in the system. `monitoring` lists the processes which have subscribed on `nodeup` and `nodedown` messages.

`monitor_nodes(Flag) -> ok`

Types:

- `Flag = bool()`

The requesting process receives `{nodeup, Node}` and `{nodedown, Node}` messages about the nodes from the immediate global group. If the flag `Flag` is set to `true` the service is turned on; `false` turns it off.

`own_nodes() -> [Node] | {error, ErrorMsg}`

Types:

- `Node = atom()`
- `ErrorMsg = term()`

Returns the names of all nodes from the immediate global group, despite of the status of the nodes. Use `info/0` to get the information of the current status of the nodes.

`registered_names({node, Node}) -> [Name] | {error, ErrorMsg}`

`registered_names({group, GlobalGroupName}) -> [Name]`

Types:

- `Name = term()`

- Node = atom()
- GlobalGroupName = atom()
- ErrorMsg = term()

Returns a lists of all globally registered names on the specified node or from the specified global group.

```
send(Name, Msg) -> Pid | {badarg, Msg} | {error, ErrorMsg}
send({node, Node}, Name, Msg) -> Pid | {badarg, Msg} | {error, ErrorMsg}
send({group, GlobalGroupName}, Name, Msg) -> Pid | {badarg, Msg} | {error, ErrorMsg}
```

Types:

- GlobalGroupName = atom()
- Msg = term()
- Name = term()
- Node = atom()
- Pid = pid()
- ErrorMsg = term()

`send/2` searches for the registered `Name` in all global groups defined, in the order of appearance in the `.config`-file, until the registered name is found or all groups are searched. If `Name` is found, the message `Msg` is sent to it. If it is not found, the function exits with reason `{badarg, {Name, Msg}}`.

`send/3` searches for the registered `Name` in either the specified node or the specified global group. If the registered name is found, the message `Msg` is sent to that process. If `Name` is not found, the function exits with reason `{badarg, {Name, Msg}}`.

```
sync() -> ok
```

`sync` synchronizes the global name servers on the nodes in the immediate global group. It also unregisters the names registered in the immediate global group on known nodes outside to the immediate global group.

If it the `global_groups` definition is invalid, the function exits with reason `{error, {'invalid global_groups definition', NodeGrpDef}}`.

```
whereis_name(Name) -> Pid | undefined | {error, ErrorMsg}
whereis_name({node, Node}, Name) -> Pid | undefined | {error, ErrorMsg}
whereis_name({group, GlobalGroupName}, Name) -> Pid | undefined | {error, ErrorMsg}
```

Types:

- GlobalGroupName = atom()
- Name = term()
- Node = atom()
- Pid = pid()

`whereis_name/1` searches for the registered `Name` in all global groups defined, in the order of appearance in the `.config`-file, until the registered name is found or all groups are searched.

`whereis_name/2` searches for the registered `Name` in either the specified node or the specified global group.

Returns either the atom `undefined`, or the `Pid` which is associated with `Name`.

```
start()
start_link() -> {ok, Pid} | {error, Reason}
```

This function starts the global group server. Normally, the server is started automatically.

```
stop() -> void()
```

Stops the global group server.

NOTE

In the situation where a node has lost its connections to other nodes in its global group but has connections to nodes in other global groups, a request from the other global group may produce an incorrect or misleading result. When this occurs the isolated node may not have accurate information, for example, about registered names in its global group.

Note also that the send function is not secure.

Distribution of applications is highly dependent of the global group definitions. It is not recommended that an application is distributed over several global groups of the obvious reason that the registered names may be moved to another global group at failover/takeover. There is nothing preventing doing this, but the application code must in such case handle the situation.

SEE ALSO

[erl\(1\)](#), [global\(3\)](#)

heart (Module)

The `heart` module sends periodic heartbeats to an external port program, which is also named `heart`. The purpose of the `heart` port program is to check that the Erlang system it is supervising is still running. If the port program has not received any heartbeats within `HEART_BEAT_TIMEOUT` (default is 60 seconds) from the last one, the system can be rebooted. Also, if the system is equipped with a hardware watchdog timer and is running Solaris, the watchdog can be used to supervise the entire system.

This module is started by the `init` module during system start-up. The `-heart` command line flag determines if the `heart` module should start .

If the system should be rebooted because of missing heart-beats, or a terminated Erlang system, the environment variable `HEART_COMMAND` has to be set before the system is started. If this variable is not set, a warning text will be printed but the system will not reboot. However, if the hardware watchdog is used, it will trigger a reboot `HEART_BEAT_BOOT_DELAY` seconds later nevertheless (default is 60).

To reboot on the WINDOWS platform `HEART_COMMAND` can be set to `heart -shutdown` (included in the Erlang delivery) or of course to any other suitable program which can activate a reboot.

The hardware watchdog will not be started under Solaris if the environment variable `HW_WD_DISABLE` is set.

The `HEART_BEAT_TIMEOUT` and `HEART_BEAT_BOOT_DELAY` environment variables can be used to configure the heart timeouts, they can be set in the operating system shell before `erl -heart` is started or can be passed on the command line like this: `erl -heart -env HEART_BEAT_TIMEOUT 30`.

The value (in seconds) must be in the range $10 < X \leq 65535$.

It should be noted that if the system clock is adjusted with more than `HEART_BEAT_TIMEOUT` seconds `heart` will timeout and try to reboot the system. This can happen for example if the system clock is adjusted automatically by use of NTP (Network Time Protocol).

Exports

```
start() -> {ok, Pid} | ignore | {error, What}
```

Types:

- `Pid` = `pid()`
- `What` = `void()`

Starts the `heart` program. This function returns `ignore` if the `-heart` command line flag is not supplied.

```
set_cmd(Cmd) -> ok | {error, {bad_cmd, Cmd}}
```

Types:

- Cmd = string()

Sets a temporary reboot command. This command is used if a HEART_COMMAND other than the one specified with the environment variable should be used in order to reboot the system. The new Erlang system will (if it misbehaves) use the environment variable HEART_COMMAND to reboot.

The length of the Cmd command string must be less than 2047 characters.

```
clear_cmd() -> ok
```

Clears the temporary boot command. If the system terminates, the normal HEART_COMMAND is used to reboot.

inet (Module)

Inet provides access to TCP/IP protocols.

Some functions returns a hostent record. Use this line in your module
`-include_lib("kernel/include/inet.hrl").`
to include the record definition.

`h_addr_list` List of addresses for this host
`h_addrtype` Type of address: `inet` or `inet6`
`h_aliases` List of aliases (additional names for host)
`h_length` Length of address in bytes
`h_name` Official name for host

Addresses as inputs to functions can be either a string or a tuple. For instance, the IP address 150.236.20.73 can be passed to `gethostbyaddr/1` either as the string "150.236.20.73" or as the tuple {150, 236, 20, 73}. Addresses returned by any function in the `inet` module will be a tuple.

Hostnames may be specified as either atoms or a strings.

Where an address family is required, valid values are `inet` (standard IPv4 addresses) or `inet6` (IPv6).

Exports

`format_error(Tag)`

Types:

- `Tag = atom()`

Returns a diagnostic error string. See the section below for possible Tag values and the corresponding strings.

`gethostbyaddr(Address) -> {ok, Hostent} | {error, Reason}`

Types:

- `Address = address()`
- `Hostent = hostent()`

Returns a hostent record given an address.

`gethostbyname(Name) -> {ok, Hostent} | {error, Reason}`

Types:

- Hostname = hostname()
- Hostent = hostent()

Returns a hostent record given a hostname.

```
gethostbyname(Name, Family) -> {ok, Hostent} | {error, Reason}
```

Types:

- Hostname = hostname()
- Family = family()
- Hostent = hostent()

Returns a hostent record given a hostname, restricted to the given address family.

```
gethostname() -> {ok, Name} | {error, Reason}
```

Types:

- Hostname = hostname()

Returns the local hostname. Will never fail.

```
sockname(Socket) -> {ok, {IP, Port}} | {error, Reason}
```

Types:

- Socket = socket()
- Address = address()
- Port = integer()

Returns the local address and port number for a socket.

```
peername(Socket) -> {ok, {Address, Port}} | {error, Reason}
```

Types:

- Socket = socket()
- Address = address()
- Port = integer()

Returns the address and port for the other end of a connection.

```
port(Socket) -> {ok, Number}
```

Types:

- Socket = socket()
- Number = integer()

Returns the local port number for a socket.

```
close(Socket) -> ok
```

Types:

- Socket = socket()

Closes a socket of any type.

```
getaddr(IP,inet) -> {ok,{A1,A2,A3,A4}} | {error, Reason}
```

Types:

- IP = {A1,A2,A3,A4} | string() | atom()
- A1 = A2 = A3 = A4 = integer()
- Reason = term()

Returns the IP-address as a tuple with integers for IP which can be an IP-address a single hostname or a fully qualified hostname. At present only IPv4 addresses (the `inet` argument) is supported, but the function is prepared to support IPv6 (`inet6`) in a near future.

```
setopts(Socket, Options) -> ok | {error, Reason}
```

Types:

- Socket = term()
- Options = list()

Sets one or more options for a socket. The following options are available:

`{active, Boolean}` If the active option is `true`, which is the default, everything received from the socket will be sent as messages to the receiving process. If the active option is set to `false` (passive mode), the process must explicitly receive incoming data by calling `gen_tcp:recv/N` or `gen_udp:recv/N` (depending on the type of socket). Note: Passive mode provides flow control; the other side will not be able send faster than the receiver can read. Active mode provides no flow control; a fast sender could easily overflow the receiver with incoming messages. Use active mode only if your high-level protocol provides its own flow control (for instance, acknowledging received messages) or the amount of data exchanged is small.

`{broadcast, Boolean}` Enable/disable permission to send broadcasts. (UDP)

`{dontroute, true|false}` Use `{dontroute, true}` to enable/disable routing bypass for outgoing messages.

`{header, Size}` This option is only meaningful if the `binary` option was specified when the socket was created. If the header option is specified, the first `Size` number bytes of data received from the socket will be elements of a list, and the rest of the data will be a binary given as the tail of the same list. If for example `Size=2` the data received will match `[Byte1,Byte2|Binary]`.

`{keepalive, Boolean}` (TCP/IP sockets) Enables periodic transmission on a connected socket, when no other data is being exchanged. If the other end does not respond, the connection is considered broken and an error message will be sent to the controlling process. Default disabled.

`{nodelay, Boolean}` If Boolean is `true`, the `TCP_NODELAY` option is turned on for the socket, which means that even small amounts of data will be sent immediately. (TCP/IP)

`{packet, PacketType}` Defines the type of packets to use for a socket. The following values are valid:

`raw` | `0` No packaging is done.

1 | 2 | 4 Packets consist of a header specifying the number of bytes in the packet, followed by that number of bytes. The length of header can be one, two, or four bytes; the order of the bytes is big-endian. Each send operation will generate the header, and the header will be stripped off on each receive operation.

asn1 | cdr | sunrm | fcgi These packet types only have effect on receiving. When sending a packet, it is the responsibility of the application to supply a correct header. On receiving, however, there will be one message sent to the controlling process for each complete packet received, and, similarly, each call to `gen_tcp:recv/N` returns one complete packet. The header is *not* stripped off. The meaning of the packet types is as follows:

`asn1` - ASN.1 BER,
`sunrm` - Sun's RPC encoding,
`cdr` - Corba,
`fcgi` - Fast CGI.

{recbuf, Integer} Gives the size of the receive buffer to use for the socket.

{reuseaddr, Boolean} Allows or disallows local reuse of port numbers. By default, reuse is disallowed.

{sndbuf, Integer} Gives the size of the send buffer to use for the socket.

ERRORS

The possible error reasons and the corresponding diagnostic strings returned by `format_error/1` are as follows:

`e2big` argument list too long
`eacces` permission denied
`eaddrinuse` address already in use
`eaddrnotavail` cannot assign requested address
`eadv` advertise error
`eafnosupport` address family not supported by protocol family
`eagain` resource temporarily unavailable
`ealign` EALIGN
`ealready` operation already in progress
`ebade` bad exchange descriptor
`ebadf` bad file number
`ebadfd` file descriptor in bad state
`ebadmsg` not a data message
`ebadr` bad request descriptor
`ebadrpc` RPC structure is bad
`ebadrqc` bad request code
`ebadslt` invalid slot

ebfont bad font file format
ebusy file busy
echild no children
echrng channel number out of range
ecomm communication error on send
econnaborted software caused connection abort
econnrefused connection refused
econnreset connection reset by peer
edeadlk resource deadlock avoided
edeadlock resource deadlock avoided
edestaddrreq destination address required
edirty mounting a dirty fs w/o force
edom math argument out of range
edotdot cross mount point
edquot disk quota exceeded
edupppkg duplicate package name
eexist file already exists
efault bad address in system call argument
efbig file too large
ehostdown host is down
ehostunreach host is unreachable
eidrm identifier removed
einit initialization error
einprogress operation now in progress
eintr interrupted system call
EINVAL invalid argument
eio I/O error
eisconn socket is already connected
eisdir illegal operation on a directory
eisnam is a named file
el2hlt level 2 halted
el2nsync level 2 not synchronized
el3hlt level 3 halted
el3rst level 3 reset
elbin ELBIN
elibacc cannot access a needed shared library
elibbad accessing a corrupted shared library
elibexec cannot exec a shared library directly
elibmax attempting to link in more shared libraries than system limit
elibscn .lib section in a.out corrupted
elnrng link number out of range

eloop too many levels of symbolic links
emfile too many open files
mlink too many links
emsgsize message too long
emultihop multihop attempted
enametoolong file name too long
enavail not available
enet ENET
enetdown network is down
enetreset network dropped connection on reset
enetunreach network is unreachable
enfile file table overflow
enoano anode table overflow
enobufs no buffer space available
enocsi no CSI structure available
enodata no data available
enodev no such device
enoent no such file or directory
enoexec exec format error
enolck no locks available
enolink link has been severed
enomem not enough memory
enomsg no message of desired type
enonet machine is not on the network
enopkg package not installed
enoprotoopt bad protocol option
enospc no space left on device
enosr out of stream resources or not a stream device
enosym unresolved symbol name
enosys function not implemented
enotblk block device required
enotconn socket is not connected
enotdir not a directory
enotempty directory not empty
enotnam not a named file
enotsock socket operation on non-socket
enotsup operation not supported
enotty inappropriate device for ioctl
enotuniq name not unique on network
enxio no such device or address
eopnotsupp operation not supported on socket

eperm not owner
epfnosupport protocol family not supported
epipe broken pipe
eproclim too many processes
eprocunavail bad procedure for program
eprogmismatch program version wrong
eprogunavail RPC program not available
eprotocol protocol error
eprototonosupport protocol not supported
eprototype protocol wrong type for socket
erange math result unrepresentable
erefused EREFUSED
eremchg remote address changed
eremdev remote device
eremote pathname hit remote file system
eremoteio remote i/o error
eremoterelease EREMOTERELEASE
eroofs read-only file system
erpcmismatch RPC version is wrong
erremote object is remote
eshutdown cannot send after socket shutdown
esocktnosupport socket type not supported
espipe invalid seek
esrch no such process
esrmnt srmount error
estale stale remote file handle
esuccess Error 0
etime timer expired
etimedout connection timed out
etoomanyrefs too many references
etxtbsy text file or pseudo-device busy
euclean structure needs cleaning
eunatch protocol driver not attached
eusers too many users
eversion version mismatch
ewouldblock operation would block
exdev cross-domain link
exfull message tables full
nxdomain the hostname or domain name could not be found

init (Module)

init is pre-loaded into the system before the system starts and it coordinates the start-up of the system. The first function evaluated at start-up is boot(Bootargs), where Bootargs is a list of the arguments supplied to the Erlang system from the local operating system. The Erlang code for the module init is always pre-loaded.

init reads a boot script which contains instructions on how to initiate the system. The default boot script (start.boot) is in the directory <ERL_INSTALL_DIR>/bin.

init contains functions to fetch command line flags, or arguments, supplied to the Erlang system.

init also contains functions to restart, reboot, and stop the system.

Exports

```
boot(BootArgs) -> void()
```

Types:

- BootArgs = [term()]

Erlang is started with the command erl <script-flags> <user-flags>.

erl is the name of the Erlang start-up script. <script-flags>, described in erl(1), are read by the script. <user-flags> are put into a list and passed as Args to boot/1.

The boot/1 function interprets the boot, mode, and s flags. These are described in COMMAND LINE FLAGS.

If the boot function finds other arguments starting with the character -, that argument is interpreted as a flag with zero or more values. It ends the previous argument. For example:

```
erl -s foo bar -charles peterson
```

This starts the Erlang system, evaluates foo:bar(), and sets the flag -charles, which has the associated value peterson.

Other arguments which are passed to the boot function, and do not fit into the above description, are passed to the init loop as plain arguments.

The special flag -- can be used to separate plain arguments to boot.

```
get_arguments() -> Flags
```

Types:

- Flags = [{Flag,[Value]}]
- Flag = atom()

- Value = string()

Returns all flags given to the system.

`get_argument(Flag) -> {ok, Values} | error`

Types:

- Flag = atom()
- Values = [FValue]
- FValue = [Value]
- Value = string()

Returns all values associated with Flag. If Flag is provided several times, each FValue is returned in preserved order.

`get_args() -> [Arg]`

Types:

- Arg = atom()

Returns the additional plain arguments as a list (possibly empty).

`restart() -> void()`

The system is restarted `inside` the running Erlang node, which means that the emulator is not restarted. All applications are taken down smoothly, all code is unloaded, and all ports are closed before the system is booted again in the same way as initially started. The same BootArgs are used again.

To limit the shutdown time, the time init is allowed to spend taking down applications, the `-shutdown_time` command line flag should be used.

`reboot() -> void()`

All applications are taken down smoothly, all code is unloaded, and all ports are closed before the Erlang node terminates. If the `-heart` system flag was given, the heart program will try to reboot the system. Refer to the heart module for more information.

In order to limit the shutdown time, the time init is allowed to spend taking down applications, the `-shutdown_time` command line flag should be used.

`stop() -> void()`

All applications are taken down smoothly, all code is unloaded, and all ports are closed before the system terminates. If the `-heart` system flag was given, the heart program is terminated before the Erlang node terminates. Refer to the heart module for more information.

In order to limit the shutdown time, the time init is allowed to spend taking down applications, the `-shutdown_time` command line flag should be used.

`get_status() -> {InternalStatus, ProvidedStatus}`

Types:

- InternalStatus = starting | started | stopping
- ProvidedStatus = term()

The current status of the `init` process can be inspected. During system start (initialization), `InternalStatus` is `starting`, and `ProvidedStatus` indicates how long the boot script has been interpreted. Each `{progress, Info}` term interpreted in the boot script affects the `ProvidedStatus` status, i.e., `ProvidedStatus` gets the value of `Info`.

```
script_id() -> Id
```

Types:

- `Id` = `term()`

Get the identity of the boot script used to boot the system. `Id` can be any Erlang term. In the delivered boot scripts, `Id` is `{Name, Vsn}`. `Name` and `Vsn` are strings.

Command Line Flags

The `init` module interprets the following flags:

- `boot File`** Specifies the name of the boot script, `File.boot`, used to start the system. Unless `File` contains an absolute path, the system searches for `File.boot` in the current and `<ERL_INSTALL_DIR>/bin` directories
If this flag is omitted, the `<ERL_INSTALL_DIR>/bin/start.boot` boot script is used.
- `boot_var Var Directory [Var Directory]`** If the boot script used contains another path variable than `SROOT`, that variable must have a value assigned in order to start the system. A boot variable is used if user applications are installed in a different location than underneath the `<ERL_INSTALL_DIR>/lib` directory. `$Var` is expanded to `Directory` in the boot script.
- `mode Mode`** The mode flag indicates if the system will load code automatically at runtime, or if all code should be loaded during system initialization. `Mode` can be either `interactive` (allow automatic code loading) or `embedded` (load all code during start-up).
- `shutdown_time Time`** Specifies how long time (in ms) the `init` process is allowed to spend shutting down the system. If `Time` milliseconds has elapsed, all processes still existing are *killed*.
If `-shutdown_time` is not specified, the default time is `infinity`.
- `s Module [Function [Args]]`** Evaluate the function during system initialization.
Function defaults to `start` and `Args` to `[]`. If the function call ends abnormally, the Erlang system stops with an error message.
The arguments after `-s` are used as arguments to Erlang functions. All arguments are passed as atoms. For example:

```
erl -s foo -s foo bar -s foo bar baz 1 2
```

This starts the Erlang system and then evaluates the following Erlang functions:

```
foo:start()
foo:bar()
foo:bar([baz, '1', '2']).
```

The functions are executed sequentially in the initialization process, which then terminates normally and passes control to the user. This means that a `-s` call which does not terminate will block further processing; to avoid this, use some variant of `spawn` in such cases.

`-init_debug` The init process writes some debug information while interpreting the boot script.

Example

```
erl -- a b -children thomas claire -ages 7 3 -- x y
1> init:get_args().
[a, b, x, y]
2> init:get_argument(children).
{ok, [{"thomas", "claire"}]}
3> init:get_argument(ages).
{ok, [{"7", "3"}]}
4> init:get_argument(silly).
error
```

See also

`erl_prim_loader(3)`, `heart(3)`

net_adm (Module)

This module contains various network utility functions.

Exports

`host_file()`

This function reads the `.hosts.erlang` file. It returns the hosts in this file as a list, or it returns `{error, Reason}` if the file cannot be found.

`dns_hostname(Host)`

This function calls epmd for the fully qualified name (DNS) of `Host`. It returns `{ok, Longhostname}` if the call is successful, or `{error, Host}` if `Host` cannot be located by DNS.

`localhost()`

This function returns the fully qualified name of the local host, if it can be found by DNS.

`names(), names(Host)`

This function returns `{ok, List}` or `{error, Reason}`. `List` is a list of tuples on the form `{Name, Port}`. For example: `net_adm:names(elrond) -> {ok, [{"foo", 61178}, {"ts", 61160}]}`.

`ping(Node)`

This function tries to set up a connection to `Node`. It returns `pang` if it fails, and `pong` if it is successful.

`world (), world (verbose)`

This function runs `epmd - names` on all hosts which are specified in the Erlang host file `.hosts.erlang`, collects the replies and then evaluates `ping` on all those nodes. Accordingly, connections are created to all nodes which are running on the hosts specified in the `.hosts.erlang` file. An error message is printed if another user node is found when this is done.

This function can be useful when a node is started, but the names of the other nodes in the network are not initially known.

`world_list (Hostlist), world_list (Hostlist, verbose)`

These functions are the same as `world/0` and `world/1`, but instead of reading the hostfile from `.hosts.erlang` the hosts are specified in `Hostlist`.

Files

The `.hosts.erlang` file consists of a number of host names written as Erlang terms. It can be located in the current work directory, `$HOME/.hosts.erlang`, or `code:root_dir()/hosts.erlang`. The format of the `.hosts.erlang` file must be one host name per line. The host names must be within quotes as shown in the following examples:

```
'super.eua.ericsson.se'.
'renat.eua.ericsson.se'.
'grouse.eua.ericsson.se'.
'gauffin1.eua.ericsson.se'.
^ (new line)
```

net_kernel (Module)

The net kernel is a system process which must be running for distributed Erlang to work. The purpose of this process is to implement parts of the BIFs `spawn/4` and `spawn_link/4`, and to provide authentication and monitoring of the network.

An Erlang system can be started from the UNIX command line as follows:

```
% erl -name foobar
```

With this command line, the `net_kernel` is started as `net_kernel:start([foobar])`.

This is done by the system itself, but the `start([Name])` function can also be called directly from the normal Erlang shell prompt, and a normal Erlang system is then converted to a node. The kernel can be shut down with the function `stop()`, but only if the kernel was not started by the system itself. The node is then converted into a normal Erlang system. All other nodes on the network will regard this as a total node crash.

If the system is started as `% erl -sname foobar`, the node name of the node will be `foobar@Host`, where Host is the short name of the host (not the fully qualified domain name). The `-name` flag gives a node with the fully qualified domain name.

Exports

`kernel_apply(M, F, A)`

As the net kernel runs in the 'user space', it is easy to provide another net kernel which is tailor made for a specific application. For example, the user supplied kernel can limit the set of registered processes which can be accessed from remote nodes, or it can spawn a new process for each `{nodeup, Node}` message and perform some application specific user authentication, a log-in procedure for example. The `kernel_apply(M, F, A)` function is supplied for this purpose.

`monitor_nodes(Flag)`

A process which evaluates this function receives copies of the `{nodeup, Node}` and `{nodedown, Node}` messages that the net kernel receives from the runtime system. The flag `Flag` is set to `true` to turn the service on, and `false` to turn it off.

`allow(NodeList)`

In a simple way, this function limits access to a node from a specific number of named nodes. A node which evaluates this function can only be accessed from nodes listed in the `NodeList` variable. Any access attempts made from nodes not listed in `NodeList` are rejected.

os (Module)

The functions in this module are operating system specific. Careless use of these functions will result in programs that will only run on a specific platform. On the other hand, with careful use these functions can be of help in enabling a program to run on most platforms.

Exports

```
cmd(Command) -> string()
```

Types:

- Command = string() | atom()

Executes `Command` in a command shell of the target OS and returns the result as a string. This function is a replacement of the previous `unix:cmd/1`; on a Unix platform they are equivalent.

Examples:

```
LsOut = os:cmd("ls"), % on unix platform
```

```
DirOut = os:cmd("dir"), % on Win32 platform
```

```
find_executable(Name) -> Filename | false
```

```
find_executable(Name, Path) -> Filename | false
```

Types:

- Name = string()
- Path = string()
- Filename = string()

These two functions look up an executable program given its name and a search path, in the same way as the underlying operating system. `find_executable/1` uses the current execution path (i.e., the environment variable `PATH` on Unix and Windows). `Path`, if given, should conform to the syntax of execution paths on the operating system. The absolute filename of the executable program `Name` is returned, or `false` if the program was not found.

```
getenv(VarName) -> Value | false
```

Types:

- Varname = string()
- Value = string()

Returns the Value of the environment variable VarName, or false if the environment variable is undefined.

`getpid() -> Value`

Types:

- Value = string()

Returns the process identifier of the current Erlang emulator in the format most commonly used by the operating system environment. Value is returned as a string containing the (usually) numerical identifier for a process. On Unix, this is typically the return value of the getpid() system call. On VxWorks, Value contains the task id (decimal notation) of the Erlang task. On Windows, the process id as returned by the GetCurrentProcessId() system call is used.

`type() -> {Osfamily,Osname} | Osfamily`

Types:

- Osfamily = atom() = win32 | unix | vxworks
- Osname = atom()

Returns the Osfamily and, in some cases, Osname of the current operating system.

On Unix, Osname will be same string that uname -s returns, but in lower case. For instance, on Solaris 1 and 2, the atom sunos will be returned.

In Windows, Osname will be either nt (on Windows NT), or windows (on Windows 95). On VxWorks Osfamily alone is returned, i.e. the atom vxworks.

Note:

Think twice before using this function. Use the filename module if you want to inspect or build file names in a portable way. Avoid matching on the Osname atom.

`version() -> {Major, Minor, Release} | VersionString`

Types:

- Major = Minor = Release = integer()
- VersionString = string()

Returns the operating system version. On most systems, this function returns a tuple, but a string will be returned instead if the system has versions which cannot be expressed as three numbers.

Note:

Think twice before using this function. If you still need to use it, always call os:type() first.

pg2 (Module)

This module implements process groups. The groups in this module differ from the groups in the module pg in several ways. In pg, each message is sent to all members in the group. In this module, each message may be sent to one, some, or all members.

A group of processes can be accessed by a common name. For example, if there is a group named foobar, there can be a set of processes (which can be located on different nodes) which are all members of the group foobar. There is no special functions for sending a message to the group. Instead, client functions should be written with the functions `get_members/1` and `get_local_members/1` to find out which process are members of the group. Then the message can be sent to one or more members of the group.

If a member terminates, it is automatically removed from the group.

Exports

`create(Name) -> void()`

Types:

- Name = term()

Creates a new, empty process group. The group is globally visible on all nodes. If the group exists, nothing happens.

`delete(Name) -> void()`

Types:

- Name = term()

Deletes a process group.

`get_closest_pid(Name) -> Pid | {error, Reason}`

Types:

- Name = term()

This is a useful dispatch function which can be used from client functions. It returns a process on the local node, if such a process exist. Otherwise, it chooses one randomly.

`get_members(Name) -> [Pid] | {error, Reason}`

Types:

- Name = term()

Returns all processes in the group `Name`. This function should be used from within a client function that accesses the group. It is then optimized for speed.

```
get_local_members(Name) -> [Pid] | {error, Reason}
```

Types:

- `Name` = term()

Returns all processes running on the local node in the group `Name`. This function should be used from within a client function that accesses the group. It is then optimized for speed.

```
join(Name, Pid) -> ok | {error, Reason}
```

Types:

- `Name` = term()

Joins the process `Pid` to the group `Name`.

```
leave(Name, Pid) -> ok | {error, Reason}
```

Types:

- `Name` = term()

Makes the process `Pid` leave the group `Name`.

```
which_groups() -> [Name]
```

Types:

- `Name` = term()

Returns a list of all known groups.

```
start()
```

```
start_link() -> {ok, Pid} | {error, Reason}
```

Starts the pg2 server. Normally, the server does not need to be started explicitly, as it is started dynamically if it is needed. This is useful during development, but in a target system the server should be started explicitly. Use configuration parameters for `kernel` for this.

See Also

`kernel(3)`, `pg(3)`

rpc (Module)

This module contains services which are similar to remote procedure calls. It also contains broadcast facilities and parallel evaluators. A remote procedure call is a method to call a function on a remote node and collect the answer. It is used for collecting information on a remote node, or for running a function with some specific side effects on the remote node.

Exports

`start()`

Starts the `rpc` server. Normally, this is not necessary because the `rpc` server is started automatically.

`stop()`

Stops the `rpc` server.

`call(Node, Module, Function, Args)`

Evaluates `apply(Mod, Fun, Args)` on the node `Node` and returns a value, or `{badrpc, Reason}` if the call fails.

`cast(Node, Module, Function, Args)`

Causes the expression `apply(Mod, Fun, Args)` to be evaluated on `Node`. No response is delivered and the process which makes the call is not suspended until the evaluation is complete, as is the case with `call/4`. The function immediately returns `true`. Example:

```
> rpc:cast(Node, erlang, halt, [])
```

This function shuts down the node `Node`.

The following function also shuts down the node, but the call returns the tuple `{badrpc, noconnection}`

```
> rpc:call(Node, erlang, halt, [])
```

`block_call(Node, Mod, Fun, Args)`

The `call/4` function causes the server at `Node` to create a new process for each request. This means that several RPCs can be active concurrently. The `rpc` server is not affected if a request does not return a value. This function can be used if the intention of the call is to block the `rpc` server from any other incoming requests until the request has been handled. The function can also be used for efficiency reasons when very small fast functions are evaluated, for example BIFs that are guaranteed not to suspend.

```
> rpc:block_call(Node, erlang, whereis, [file_server]),
```

Returns the Pid of the file server at `Node`.

`server_call(Node, Name, ReplyWrapper, Msg)`

This function is used when interacting with a server called `Name` at node `Node`. It is assumed that the server receives messages in the format `{From, Request}` and replies in the format `From ! {ReplyWrapper, node(), Reply}`. This function makes such a server call and ensures that the entire call is packed into an atomic transaction which either succeeds or fails. It never hangs, unless the server itself hangs.

The function, for example, is used by the `call/4` function to interact with the `rpc` server at a remote node. The function returns `{error, Reason}`, or the answer as produced by the server `Name`.

`abcast(Name, Mess)`

Broadcasts the message `Mess` asynchronously to the registered process `Name` on all nodes, including the current node.

`abcast(Nodes, Name, Mess)`

The same as `abcast/2`, but only to the nodes `Nodes`.

`sbcast(Name, Msg)`

Broadcasts to all nodes synchronously and returns a list of the nodes which have `Name` as a registered server. Returns `{Goodnodes, Badnodes}`.

It is synchronous in the sense that it is known that all servers have received the message when we return from the call. It is not possible to know that the servers have actually processed the message.

Any further messages sent to the servers, after this function has returned, will be received by all servers after this message .

`sbcast(Nodes, Name, Msg)`

As `sbcast/2` but only to the nodes in `Nodes`.

`eval_everywhere(Mod, Fun, Args)`

Evaluates the expression `apply(Mod, Fun, Args)` on all nodes. No answers are collected.

`eval_everywhere(Nodes, Mod, Fun, Args)`

Evaluates the expression `apply(Mod, Fun, Args)` on the nodes `Nodes`.

`multicall(M, F, A)`

In contrast to an RPC, a multicall is an RPC which is sent concurrently from one client to multiple servers. This is useful for collecting some information from a set of nodes, or for calling a function on a set of nodes to achieve some side effects. It is semantically the same as iteratively making a series of RPCs on all the nodes, but the multicall is faster as all the requests are sent at the same time and are collected one by one as they come back.

The function `multicall/3` evaluates the expression `apply(M, F, A)` on all nodes and collects the answers. It returns `{Replies, Badnodes}`, where `Badnodes` is a list of the nodes that terminated during computation and `Replies` is a list of the return values. This is useful when new object code is to be loaded on all nodes in the network.

```
%% Find object code for module Mod
{Mod, File, Bin} = code:get_object_code(Mod),

%% and load it on all nodes including this one
{Replies, _} = rpc:multicall(code, load_binary, [Mod, File, Bin]),

%% and then maybe check the Replies list.
```

This is an example of the side effects the RPCs may produce.

`multicall(Nodes, M, F, A)`

Executes the multicall only on the nodes `Nodes`.

`multi_server_call(Name, Msg)`

This function is used by the `multicall/3` function when it interacts with the `rpc` server. The function can, of course, also be used for interacting with other servers.

The function sends `Msg` to `Name` on all nodes, and collects the answers. It returns `.br {Replies, Badnodes}`, where `Badnodes` is a list of the nodes which failed during the call. This function assumes that if a request sent to a server called `Name`, the server replies in the form `{Name, node(), Reply}`. Otherwise, the function will hang. It also assumes that the server receives messages in the form `{From, Msg}`, and then replies as `.br From ! {Name, node(), Reply}`.

The function also hangs if any one of the servers involved crash, or do not exist, during the call. This function, then, assumes that the servers are stable. If any of the nodes involved crash, the function still works and the crashed node appears in the `Badnodes` list of the return value.

The replies are not ordered in any particular way.

`multi_server_call(Nodes, Name, Msg)`

The same as above, but `Msg` is only sent to `Nodes`.

`safe_multi_server_call(Name, Msg)`

The same as the `multi_server_call/2`, except that this function handles the case where the remote node exists, but no server called `Name` exists there. This call is also slightly slower than `multi_server_call/2` since all request go via the `rpc` server at the remote sites.

`safe_multi_server_call(Nodes, Name, Msg)`

The same as above, but only on the nodes `Nodes`.

`async_call(Node, Mod, Fun, Args)`

Call streams with promises is a type of `rpc` which does not suspend the caller until the result is finished. They return a `Key` which can be used at a later stage to collect the value. The key can be viewed as a promise to deliver the answer. The expression `apply(Mod, Fun, Args)` is evaluated for this function on `Node`. Returns `Key` which can be used in a subsequent `yield/1` (see below).

`yield(Key)`

Delivers the promised answer from a previous `async_call` operation. If the answer is available, it is returned immediately. Otherwise, the caller of `yield/1` is suspended until the answer arrives from `Node`.

`nb_yield(Key)`

This is a non-blocking version of `yield`. It returns either the atom `timeout`, or the tuple `{value, V}`, if the computation is finished.

`parallel_eval(ListOfTuples)`

Evaluates the list of size 3 tuples `ListOfTuples`. Each tuple must be of the type `{Mod, Fun, Args}`. Each tuple is sent for evaluation to neighboring nodes, and the replies are collected and returned as a list of individual values. The return values are presented in the same order as the original list `ListOfTuples`.

`pmap({M, F}, Extraargs, List)`

Takes exactly the same arguments and has the same return value as the `lists:map/3` function, except that everything is evaluated in parallel on different nodes.

`pinfo(Pid)`

Location transparent version of `process_info/1`.

`pinfo(Pid, Item)`

Location transparent version of `process_info/2`.

seq_trace (Module)

Sequential tracing makes it possible to trace all messages resulting from one initial message. Sequential tracing is completely independent of the ordinary tracing in Erlang, which is controlled by the `erlang:trace/3` BIF. See the chapter "What is Sequential Trace" [page 156] below for more information about what sequential tracing is and how it can be used.

`seq_trace` provides functions which control all aspects of sequential tracing. There are functions for activation, deactivation, inspection and for collection of the trace output.

Note:

The implementation of sequential tracing is in beta status. This means that the programming interface still might undergo minor adjustments (possibly incompatible) based on feedback from users.

Exports

```
set_token(Component, ComponentValue) -> {Component, PreviousValue}
```

Types:

- Component = label | serial | Flag
- Flag = send | 'receive' | print | timestamp
- ComponentValue = FlagValue | LabelValue | SerialValue
- FlagValue = bool() (for Flag)
- LabelValue = integer() (for label)
- SerialValue = {Previous, Current}
- Previous = Current = integer()

Sets the individual `Component` of the trace token to `ComponentValue`. Returns the previous value of the trace token `Component`. The valid `Component`, `ComponentValue` combinations are:

`label`, `integer()` The `label` component is an integer which identifies all events belonging to the same sequential trace. If several sequential traces can be active simultaneously `label` is used to identify the separate traces. Default is 0.

`send`, `bool()` A trace token flag (true | false) which enables/disables tracing on message sending. Default is false.

`'receive'`, `bool()` A trace token flag (true | false) which enables/disables tracing on message reception. Default is false.

print, `bool()` A trace token flag (`true` | `false`) which enables/disables tracing on explicit calls to `seq_trace:print/1`. Default is `false`.

timestamp, `bool()` A trace token flag (`true` | `false`) which enables/disables a timestamp to be generated for each traced event. Default is `false`.

serial, `SerialValue` `SerialValue = {Previous, Current}`. The `serial` component contains counters which enables the traced messages to be sorted, should never be set explicitly by the user as these counters are updated automatically. Default is `{0, 0}`.

`set_token(Token) -> PreviousToken`

Types:

- `Token = PreviousToken = term() | []`

Sets the trace token for the current process to `Token`. If `Token = []` then tracing is disabled, otherwise `Token` should be an Erlang term returned from `get_token/0` or `set_token/1`. `set_token/1` can be used to temporarily exclude message passing from the trace by setting the trace token to empty like this:

```
OldToken = seq_trace:set_token([]), % set to empty and save
          % old value
% do something that should not be part of the trace
io:format("Exclude the signalling caused by this~n"),
seq_trace:set_token(OldToken), % activate the trace token again
...
```

Returns the previous value of the trace token.

`get_token(Component) -> {Component, ComponentValue}`

Types:

- `Component = label | serial | Flag`
- `ComponentValue = FlagValue | LabelValue | SerialValue`
- `Flag = send | 'receive' | print | timestamp`
- `FlagValue = bool()` (for `Flag`)
- `LabelValue = integer()` (for `label`)
- `SerialValue = {Previous, Current}` (for `serial`)
- `Previous = Current = integer()`

Returns the value of the trace token component `Component`.

`get_token() -> TraceToken`

Types:

- `TraceToken = term() | []`

Returns the value of the trace token for the current process. If `[]` is returned it means that tracing is not active. Any other value returned is the value of an active trace token. The value returned can be used as input to the `set_token/1` function.

`print(TraceInfo) -> void`

Types:

- TraceInfo = term()

Puts the Erlang term TraceInfo into the sequential trace output if the process currently is executing within a sequential trace and the print flag of the trace token is set.

```
reset_trace() -> void
```

Sets the trace token to empty for all processes in the node. The process internal counters used to create the serial of the trace token is set to 0. The trace token is set to empty for all messages in message queues. Together this will effectively stop all ongoing sequential tracing in the Erlang node.

```
set_system_tracer(ProcessOrPortId) -> PreviousId
```

Types:

- Pid = PreviousId = pid() | port() | false

Sets the system tracer. The system tracer can be either a pid or port denoted by ProcessOrPortId. Returns the previous value (which can be false if no system tracer is active). The function will generate {'EXIT', {badarg, Info}} if Pid is not the pid of an existing local process.

```
get_system_tracer() -> pid() | port() | false
```

Returns the pid or port identifier of the current system tracer or false if no system tracer is activated.

Trace Messages Sent To the System Tracer

The format of the messages are:

```
{seq_trace, Label, SeqTraceInfo, TimeStamp}
```

or

```
{seq_trace, Label, SeqTraceInfo}
```

depending on whether the timestamp flag of the trace token is set to true or false.
Where :

```
Label = integer()
```

```
TimeStamp = {Seconds, Milliseconds, Microseconds}
```

```
Seconds = Milliseconds = Microseconds = integer()
```

The SeqTraceInfo can have the following formats:

```
{send, Serial, From, To, Message} Used when a process From with its trace token flag print set to true has sent a message.
```

```
{'receive', Serial, From, To, Message} Used when a process To receives a message with a trace token that has the 'receive' flag set to true.
```

```
{print, Serial, From, _, Info} Used when a process From has called seq_trace:print(Label, Info) and has a trace token with print set to true and label set to Label.
```

```
Serial = {PreviousSerial, ThisSerial}
PreviousSerial = ThisSerial = integer()
From = To = pid()
```

Serial is a tuple consisting of two integers where the first PreviousSerial denotes the serial counter passed in the last received message which carried a trace token. If the process is the first one in a new sequential trace the PreviousSerial is set to the value of the process internal “trace clock”. The second integer ThisSerial is the serial counter that a process sets on outgoing messages and it is based on the process internal “trace clock” which is incremented by one before it is attached to the trace token in the message.

What is Sequential Tracing

Sequential tracing is a way to trace a sequence of messages sent between different local or distributed processes where the sequence is initiated by one single message. In short it works like this:

Each process has a *trace token* which can be empty or not empty. When not empty the trace token can be seen as the tuple {Label, Flags, Serial, From}. The trace token is passed invisibly with each message.

In order to start a sequential trace the user must explicitly set the trace token in the process that will send the first message in a sequence.

The trace token of a process is automatically set to empty each time the process enters a receive statement but will be set to a value again if the received message carries a nonempty trace token.

On each Erlang node a process can be set as the *system tracer*. This process will receive trace messages each time a message with a trace token is sent or received (if the trace token flag send or ‘receive’ is set). The system tracer can then print each trace event, write it to a file or whatever suitable.

Note:

The system tracer will only receive those trace events that occur locally within the Erlang node. To get the whole picture of a sequential trace that involves processes on several Erlang nodes, the output from the system tracer on each involved node must be merged (off line).

In the following sections Sequential Tracing and its most fundamental concepts are described.

Trace Token

Each process has a current trace token. Initially the token is empty. When the process sends a message to another process, a copy of the current token will be sent “invisibly” along with the message. The current token of a process is set in two ways, either

1. explicitly by the process itself, through a call to `seq_trace:set_token`, or
2. when a message is received.

In both cases the current token will be set. In particular, if the token of a message received is empty, the current token of the process is set to empty.

A trace token contains a label, and a set of flags. Both the label and the flags are set in 1 and 2 above.

Serial

The trace token contains a component which we call the `Serial` which consists of two integers `Previous` and `Current`. The purpose of `Serial` is uniquely identify each traced event within a trace sequence and to order the messages chronologically and in the different branches if any.

The algorithm for updating `Serial` can be described as follows:

Let each process have two counters `prev_cnt` and `curr_cnt` which both are set to 0 when a process is created. The counters are updated at the following occasions:

- *When the process is about to send a message and the trace token is not empty.*

Let the `Serial` of the trace token be `tprev` and `tcurr`.

```
curr_cnt := curr_cnt + 1
tprev := prev_cnt
tcurr := curr_cnt
```

The trace token with `tprev` and `tcurr` is then passed along with the message.

- *When the process calls `seq_trace:print(Label, Info)` the Label matches the label part of the trace token and the trace token print flag is true.*

The same algorithm as for send above.

- *When a message is received and contains a nonempty trace token.*

The process trace token is set to the trace token from the message.

Let the `Serial` of the trace token be `tprev` and `tcurr`.

```
if (curr_cnt < tcurr )
    curr_cnt := tcurr
    prev_cnt := tprev
```

The `curr_cnt` of a process is incremented each time the process is involved in a sequential trace. The counter can reach its limit (27 bits) if a process is very long-lived and is involved in much sequential tracing. If the counter overflows it will not be possible to use the `Serial` for ordering of the trace events. To prevent the counter from overflowing in the middle of a sequential trace the function `seq_trace:reset_trace/0` can be called to reset the `prev_cnt` and `curr_cnt` of all processes in the Erlang node. This function will also set all trace tokens in processes and their message queues to empty and will thus stop all ongoing sequential tracing.

Performance considerations

The performance degradation for a system which is enabled for Sequential tracing is negligible as long as no tracing is activated. When tracing is activated there will of course be an extra cost for each traced message but all other messages will be unaffected.

Ports

Sequential tracing is not performed across ports.

If the user for some reason wants to pass the trace token to a port this has to be done manually in the code of the port controlling process. The port controlling processes have to check the appropriate sequential trace settings (as obtained from `seq_trace:get_token/1` and include trace information in the message data sent to their respective ports.

Similarly, for messages received from a port, a port controller has to retrieve trace specific information, and set appropriate sequential trace flags through calls to `seq_trace:set_token/2`.

Distribution

Sequential tracing between nodes is performed transparently. This applies to C-nodes built with Erl_interface too. A C-node built with Erl_interface only maintains one trace token which means that the C-node will appear as one process from the sequential tracing point of view.

In order to be able to perform sequential tracing between distributed Erlang nodes, the distribution protocol has been extended (in a backward compatible way). An Erlang node which supports sequential tracing can communicate with an older (OTP R3B) node but messages passed within that node can of course not be traced.

Example of Usage

The example shown here will give rough idea of how the new primitives can be used and what kind of output it will produce.

Assume that we have an initiating process with Pid = <0.30.0> like this:

```

-module(seqex).
-compile(export_all).

loop(Port) ->
    receive
        {Port,Message} ->
            seq_trace:set_token(label,17),
            seq_trace:set_token('receive',true),
            seq_trace:set_token(print,true),
            seq_trace:print(17,"***** Trace Started *****"),
            call_server ! {self(),the_message};
        {ack,Ack} ->
            ok
    end,
    loop(Port).

```

And a registered process 'call_server' with Pid = <0.31.0> like this:

```

loop() ->
    receive
        {PortController,Message} ->
            Ack = {received, Message},
            seq_trace:print(17,"We are here now"),
            PortController ! {ack,Ack}
    end,
    loop().

```

A possible output from the system's sequential_tracer (inspired by AXE-10 and MD-110) could look like:

```

17:<0.30.0> Info {0,1} WITH
"***** Trace Started *****"
17:<0.31.0> Received {0,2} FROM <0.30.0> WITH
{<0.30.0>,the_message}
17:<0.31.0> Info {2,3} WITH
"We are here now"
17:<0.30.0> Received {2,4} FROM <0.31.0> WITH
{ack,{received,the_message}}

```

The implementation of a system tracer process that produces the printout above could look like this:

```

tracer() ->
    receive
        {seq_trace,Label,TraceInfo} ->
            print_trace(Label,TraceInfo,false);
        {seq_trace,Label,TraceInfo,Ts} ->
            print_trace(Label,TraceInfo,Ts);
        Other -> ignore
    end,
    tracer().

print_trace(Label,TraceInfo,false) ->
    io:format("~p:",[Label]),
    print_trace(TraceInfo);
print_trace(Label,TraceInfo,Ts) ->

```

```

io:format("~-p ~p:",[Label,Ts]),
print_trace(TraceInfo).

print_trace({print,Serial,From,_,Info}) ->
    io:format("~-p Info ~p WITH~n~p~n", [From,Serial,Info]);
print_trace({'receive',Serial,From,To,Message}) ->
    io:format("~-p Received ~p FROM ~p WITH~n~p~n",
              [To,Serial,From,Message]);
print_trace({send,Serial,From,To,Message}) ->
    io:format("~-p Sent ~p TO ~p WITH~n~p~n",
              [From,Serial,To,Message]).

```

The code that creates a process that runs the tracer function above and sets that process as the system tracer could look like this:

```

start() ->
    Pid = spawn(?MODULE,tracer,[]),
    seq_trace:set_system_tracer(Pid), % set Pid as the system tracer
    ok.

```

With a function like `test/0` below the whole example can be started.

```

test() ->
    P = spawn(?MODULE, loop, [port]),
    register(call_server, spawn(?MODULE, loop, [])),
    start(),
    P ! {port,message}.

```

user (Module)

`user` is a server which responds to all the messages defined in the I/O interface. The code in `user.erl` can be used as a model for building alternative I/O servers.

Exports

`start() -> void()`

Starts the basic standard I/O server for the user interface port.

wrap_log_reader (Module)

`wrap_log_reader` is a function to read internally formatted wrap disk logs, refer to `disk_log(3)`. `wrap_log_reader` does not interfere with `disk_log` activities; there is however a known bug in this version of the `wrap_log_reader`, see chapter bugs below.

A wrap disk log file consists of several files, called index files. A log file can be opened and closed. It is also possible to open just one index file separately. If an non-existent or a non-internally formatted file is opened, an error message is returned. If the file is corrupt, no attempt to repair it will be done but an error message is returned.

If a log is configured to be distributed, there is a possibility that all items are not logged on all nodes. `wrap_log_reader` does only read the log on the called node, it is entirely up to the user to be sure that all items are read.

Exports

```
chunk(Continuation)
chunk(Continuation, N) -> {Continuation2, Terms} | {Continuation2, Terms, Badbytes} |
    {Continuation2, eof} | {error, Reason}
```

Types:

- Continuation = continuation()
- N = int() > 0 | infinity
- Continuation2 = continuation()
- Terms= [term()]
- Badbytes = integer()

This function makes it possible to efficiently read the terms which have been appended to a log. It minimises disk I/O by reading large 8K chunks from the file.

The first time `chunk` is called an initial continuation returned from the `open/1`, `open/2` must be provided.

When `chunk/3` is called, `N` controls the maximum number of terms that are read from the log in each chunk. Default is `infinity`, which means that all the terms contained in the 8K chunk are read. If less than `N` terms are returned, this does not necessarily mean that end of file is reached.

The `chunk` function returns a tuple `{Continuation2, Terms}`, where `Terms` is a list of terms found in the log. `Continuation2` is yet another continuation which must be passed on into any subsequent calls to `chunk`. With a series of calls to `chunk` it is then possible to extract all terms from a log.

The `chunk` function returns a tuple `{Continuation2, Terms, Badbytes}` if the log is opened in read only mode and the read chunk is corrupt. `Badbytes` indicates the number of non-Erlang terms found in the chunk. Note also that the log is not repaired. `chunk` returns `{Continuation2, eof}` when the end of the log is reached, and `{error, Reason}` if an error occurs.

The returned continuation may or may not be valid in the next call to `chunk`. This is because the log may wrap and delete the file into which the continuation points. To make sure this does not happen, the log can be blocked during the search.

```
close(Continuation) -> ok
```

Types:

- `Continuation = continuation()`

This function closes a log file properly.

```
open(Filename) -> OpenRet
```

```
open(Filename, N) -> OpenRet
```

Types:

- `File = string() | atom()`
- `N = integer()`
- `OpenRet = {ok, Continuation} | {error, Reason}`
- `Continuation = continuation()`

`Filename` specifies the name of the file which is to be read.

`N` specifies the index of the file which is to be read. If `N` is omitted the whole wrap log file will be read; if it is specified only the specified index file will be read.

The `open` function returns `{ok, Continuation}` if the log/index file was successfully opened. The `Continuation` is to be used when chunking or closing the file.

The function returns `{error, Reason}` for all errors.

Bugs

This version of the `wrap_log_reader` does not detect if the `disk_log` wraps to a new index file between a `wrap_log_reader:open` and the first `wrap_log_reader:chunk`. In this case the chuck will actually read the last logged items in the log file, because the opened index file was truncated by the `disk_log`.

See Also

`disk_log(3)`

app (File)

The *application resource file* specifies the resources an application uses, and how the application is started. There must always be one application resource file for each application in the system.

This file is read when an application is loaded, or by the start script generating tools (`systools`).

FILE SYNTAX

The application resource file is called `Name.app` where `Name` is the name of the application. The file should be located in the `ebin` directory for the application.

The `.app` file contains one single Erlang term, which is called an *application specification*. The file has the following syntax:

```
{application, ApplName,  
 [{description, String},  
 {vsn, String},  
 {id, String},  
 {modules, [{Mod1,Vsn1}, Mod2, {Mod3,Vsn3} ... , {ModN,VsnN}]},  
 {maxP, Int | infinity},  
 {maxT, Seconds | infinity},  
 {registered, [Name1, Name2, ...]},  
 {applications, [Appl1, Appl2, ..., ApplN]},  
 {included_applications, [Appl1, Appl2, ..., ApplN]},  
 {env, [{Par1, Val1}, {Par2, Val2} ... , {ParN, ValN}]},  
 {mod, {Mod, StartArgs}},  
 {start_phases, [{Phase, PhaseArgs}]}}].
```

The keys have the following meanings:

- `Name` = `atom()` is the name of the application.
- `Description` = `string()` is a textual description of the application.
- `Vsn` = `string()` is the version of the application. This string must be a valid filename.
- `Id` = `string()` is the product identification of the application.
- `Modules` = `[Mod1 | {Mod1, Vsn1}]` is a list of all the modules and their versions introduced by this application. A module can be listed without version, only the name of the module is stated. A module can only be defined in one application.
- `MaxT` = `int() | infinity` is the maximum time that the application can run (or the atom `infinity`). The key `maxT` is optional and defaults to `infinity`.

- `Registered` = `[atom()]` is a list of all the names of registered processes started in this application.
- `applications` = `[atom()]` is a list of applications which must be started before this application is started. Most applications have dependencies to the `kernel` and `stdlib` applications.
- `included_applications` = `[atom()]` is a list of applications which are included by this application. An included application is loaded, but not started, by the `application_controller`. Processes implemented in an included application should be placed underneath a supervisor in the including application. This key is optional and defaults to `[]`.
- `env` is a list of the environment variables in the application. Each parameter `ParX` is an atom, and the associated `ValX` can be any term. The `env` key is optional and defaults to an empty list.
- `mod` is the application callback module of the application behaviour. The application master starts the application by evaluating the function `Mod:start(Type, StartArgs)`. When the application has stopped, by command or because it terminates, the application master calls `Mod:stop(State)` to let the application clean up. If no `State` was returned from `Mod:start/2`, `Mod:stop([])` is called.
The `mod` key should be omitted for applications which are code libraries, such as the `stdlib` application. These applications have no dynamic behaviour of their own and should not have a start function.
- `start_phases` is a list of start phases and the attached start arguments for the application. The application master starts the application by evaluating the function `Mod:start_phase(Phase, Type, PhaseArgs)` for each defined start phase. `Mod` is the same callback module as defined in the `mod` key. Each parameter `Phase` is an atom, and the associated `PhaseArgs` is a list of any terms. The key `start_phases` is optional, and the behaviour of the system is dependent if the key is defined or not, refer to application (3).

SEE ALSO

`application(3)`, `systools(3)`

config (File)

A *configuration file* contains values for configuration parameters for the applications in the system. The command `erl -config Name` tells the system to use data in the system configuration file `Name.config` to override the arguments contained in the application resource files for the set of applications used by this system.

An application should call `application:get_env(AppName, Parameter)` to retrieve the values for the configuration parameters.

The parameters can also be overridden from the command line:

```
erl -AppName Par1 Val1 Par2 Val2 ...
```

Note:

Each term should be an Erlang term. However, in the Unix shell, the term must be enclosed in single quotation marks. For example: '{file, "a.log"}'.

FILE SYNTAX

The configuration file is called `Name.config` where `Name` is the name of the application.

The file has the following syntax:

```
[{AppName, [{Par, Val}]}].
```

There is one tuple for each application. The second element in each tuple is a list of configuration parameters and their values.

- `AppName = atom()` is the name of the application.
- `Par = atom()` is the name of a configuration parameter.
- `Val = term()` is the value of the configuration parameter.

SEE ALSO

`application(3)`, `systools(3)`

Index

Modules are typed in *this way*.
Functions are typed in *this way*.

```
abcast/2                                disk_log , 48
    rpc , 150
abcast/3                                alog_terms/2
    rpc , 150                             disk_log , 48
abs/1                                    application
    erlang , 68                           get_all_env/0, 29
accept/1                                  get_all_env/1, 29
    gen_tcp , 116                          get_all_key/0, 29
accept/2                                  get_all_key/1, 29
    gen_tcp , 116                          get_application/0, 30
add_path/1                                get_application/1, 30
    code , 40                           get_env/1, 30
add_patha/1                               get_env/2, 30
    code , 40                           get_key/1, 30
add_paths/1                               get_key/2, 30
    code , 40                           load/1, 30
add_pathsa/1                              load/2, 30
    code , 41                           loaded_applications/0, 31
add_pathsz/1                              Module:config_change/3, 33
    code , 40                           Module:start/2, 34
add_pathz/1                               Module:start_phase/3, 34
    code , 40                           Module:stop/1, 35
add_report_handler/1                      permit/2, 31
    error_logger , 100                     start/1, 32
add_report_handler/2                      start/2, 32
    error_logger , 100                     start_type/0, 32
add_slave/1                               stop/1, 32
    erl_boot_server , 59                     takeover/2, 33
all_loaded/0                             which_applications/0, 33
    code , 43                           apply/3
allow/1                                   erlang , 68
    net_kernel , 144
alog/2                                    async_call/4
    rpc , 152
atom_to_list/1                           auth
    erlang , 68                           cookie/0, 38
exists/1, 37                            cookie/1, 38
```

```
is_auth/1, 37
node_cookie/2, 38
open/1, 37
start/0, 37
stop/0, 37
file , 102
change_owner/3
file , 102
change_size/2
disk_log , 50
change_time/2
file , 102
change_time/3
file , 102
chunk/1
wrap_log_reader , 162
chunk/2
disk_log , 50
wrap_log_reader , 162
chunk/3
disk_log , 50
chunk_step/3
disk_log , 51
clash/0
code , 45
clear_cmd/0
heart , 130
close/1
disk_log , 51
file , 102
gen_tcp , 116
gen_udp , 119
inet , 132
wrap_log_reader , 163
cmd/1
os , 145
code
add_path/1, 40
add_patha/1, 40
add_paths/1, 40
add_pathsa/1, 41
add_pathsz/1, 40
add_pathz/1, 40
all_loaded/0, 43
clash/0, 45
compiler_dir/0, 44
del_path/1, 41
delete/1, 42
delete_interpret/1, 45
ensure_loaded/1, 42
get_object_code/1, 44
get_path/0, 40
balog/2
disk_log , 48
balog_terms/2
disk_log , 48
binary_to_list/1
erlang , 68
binary_to_list/3
erlang , 68
binary_to_term/1
erlang , 69
block/1
disk_log , 49
block/2
disk_log , 49
block_call/4
rpc , 149
blog/2
disk_log , 53
blog_terms/2
disk_log , 54
boot/1
init , 138
breopen/3
disk_log , 57
btruncate/2
disk_log , 58
call/4
rpc , 149
cast/4
rpc , 149
change_group/2
file , 102
change_header/2
disk_log , 49
change_notify/3
disk_log , 49
change_owner/2
```

```

interpret/1, 45
interpret_binary/3, 45
interpreted/0, 46
interpreted/1, 46
is_loaded/1, 42
lib_dir/0, 43
lib_dir/1, 43
load_abs/1, 41
load_binary/3, 43
load_file/1, 41
objfile_extension/0, 44
priv_dir/1, 44
purge/1, 42
replace_path/2, 41
root_dir/0, 43
set_path/1, 40
soft_purge/1, 42
start/0, 39
start/1, 39
start_link/0, 39
start_link/1, 39
stick_dir/1, 44
stop/0, 43
unstick_dir/1, 45
which/1, 45

compiler_dir/0
    code , 44

concat_binary/1
    erlang , 69

connect/3
    gen_tcp , 116

connect/4
    gen_tcp , 116

consult/1
    file , 102

controlling_process/2
    gen_tcp , 117
    gen_udp , 119

cookie/0
    auth , 38

cookie/1
    auth , 38

create/1
    pg2 , 147

date/0
    erlang , 69

del_dir/1
    file , 103
    del_lock/1
        global , 121
    del_lock/2
        global , 121
    del_path/1
        code , 41
    delete/1
        code , 42
        file , 103
        pg2 , 147
    delete_interpret/1
        code , 45
    delete_report_handler/1
        error_logger , 100
    delete_slave/1
        erl_boot_server , 60

disk_log
    alog/2, 48
    alog_terms/2, 48
    balog/2, 48
    balog_terms/2, 48
    block/1, 49
    block/2, 49
    blog/2, 53
    blog_terms/2, 54
    breopen/3, 57
    btruncate/2, 58
    change_header/2, 49
    change_notify/3, 49
    change_size/2, 50
    chunk/2, 50
    chunk/3, 50
    chunk_step/3, 51
    close/1, 51
    format_error/1, 52
    inc_wrap_file/1, 52
    info/1, 52
    log/2, 53
    log_terms/2, 54
    open/1, 54
    reopen/2, 57
    reopen/3, 57
    sync/1, 57
    truncate/1, 58
    truncate/2, 58
    unblock/1, 58

dns_hostname/1
    net_adm , 142

```

```

element/2
  erlang , 70

ensure_loaded/1
  code , 42

erase/0
  erlang , 70

erase/1
  erlang , 70

erl_boot_server
  add_slave/1, 59
  delete_slave/1, 60
  start/1, 59
  start_link/1, 59
  which_slaves/0, 60

erl_dll
  format_error/1, 62
  load_driver/2, 61
  loaded_drivers/0, 62
  start/0, 61
  start_link/0, 61
  stop/0, 61
  unload_driver/1, 61

erl_prim_loader
  get_file/1, 64
  get_path/0, 65
  set_path/1, 65
  start/3, 64

erlang
  abs/1, 68
  apply/3, 68
  atom_to_list/1, 68
  binary_to_list/1, 68
  binary_to_list/3, 68
  binary_to_term/1, 69
  concat_binary/1, 69
  date/0, 69
  element/2, 70
  erase/0, 70
  erase/1, 70
  erlang:cancel_timer/1, 69
  erlang:check_process_code/2, 69
  erlang:delete_module/1, 70
  erlang:demonitor/1, 70
  erlang:disconnect_node/1, 70
  erlang:fun_info/1, 72
  erlang:fun_info/2, 72
  erlang:fun_to_list/1, 72
  erlang:get_cookie/0, 73
  erlang:hash/2, 74

                                         erlang:info/1, 74
                                         erlang:load_module/2, 76
                                         erlang:localtime/0, 76
                                         erlang:localtime_to_universaltime/1,
                                         76
                                         erlang:module_loaded/1, 77
                                         erlang:monitor/2, 77
                                         erlang:port_info/2, 80
                                         erlang:ports/0, 81
                                         erlang:pre_loaded/0, 81
                                         erlang:process_display/2, 81
                                         erlang:purge_module/1, 83
                                         erlang:resume_process/1, 84
                                         erlang:send_after/3, 85
                                         erlang:set_cookie/2, 85
                                         erlang:start_timer/3, 88
                                         erlang:suspend_process/1, 88
                                         erlang:system_flag/2, 88
                                         erlang:trace/3, 89
                                         erlang:trace_info/2, 91
                                         erlang:trace_pattern/2, 92
                                         erlang:universaltime/0, 93
                                         erlang:universaltime_to_localtime/1,
                                         93
                                         exit/1, 71
                                         exit/2, 71
                                         fault/1, 71
                                         fault/2, 71
                                         float/1, 72
                                         float_to_list/1, 72
                                         get/0, 73
                                         get/1, 73
                                         get_keys/1, 73
                                         group_leader/0, 73
                                         group_leader/2, 73
                                         halt/0, 73
                                         halt/1, 74
                                         hd/1, 74
                                         integer_to_list/1, 74
                                         is_alive/0, 74
                                         is_process_alive/1, 74
                                         length/1, 74
                                         link/1, 75
                                         list_to_atom/1, 75
                                         list_to_binary/1, 75
                                         list_to_float/1, 75
                                         list_to_integer/1, 75
                                         list_to_pid/1, 75
                                         list_to_tuple/1, 76
                                         make_ref/0, 77
                                         monitor_node/2, 77
                                         node/0, 78
                                         node/1, 78

```

```

nodes/0, 78
now/0, 78
open_port/2, 78
pid_to_list/1, 80
process_flag/2, 81
process_flag/3, 82
process_info/1, 82
process_info/2, 83
processes/0, 83
put/2, 84
register/2, 84
registered/0, 84
round/1, 85
self/0, 85
setelement/3, 85
size/1, 85
spawn/1, 86
spawn/2, 86
spawn/3, 86
spawn/4, 86
spawn_link/1, 86
spawn_link/2, 86
spawn_link/3, 86
spawn_link/4, 87
spawn_opt/4, 87
split_binary/2, 87
statistics/1, 88
term_to_binary/1, 89
throw/1, 89
time/0, 89
tl/1, 89
trunc/1, 93
tuple_to_list/1, 93
unlink/1, 93
unregister/1, 94
whereis/1, 94

erlang:cancel_timer/1
    erlang, 69
erlang:check_process_code/2
    erlang, 69
erlang:delete_module/1
    erlang, 70
erlang:demonitor/1
    erlang, 70
erlang:disconnect_node/1
    erlang, 70
erlang:fun_info/1
    erlang, 72
erlang:fun_info/2

erlang , 72
erlang:fun_to_list/1
    erlang, 72
erlang:get_cookie/0
    erlang, 73
erlang:hash/2
    erlang, 74
erlang:info/1
    erlang, 74
erlang:load_module/2
    erlang, 76
erlang:localtime/0
    erlang, 76
erlang:localtime_to_universaltime/1
    erlang, 76
erlang:module_loaded/1
    erlang, 77
erlang:monitor/2
    erlang, 77
erlang:port_info/2
    erlang, 80
erlang:ports/0
    erlang, 81
erlang:pre_loaded/0
    erlang, 81
erlang:process_display/2
    erlang, 81
erlang:purge_module/1
    erlang, 83
erlang:resume_process/1
    erlang, 84
erlang:send_after/3
    erlang, 85
erlang:set_cookie/2
    erlang, 85
erlang:start_timer/3
    erlang, 88
erlang:suspend_process/1
    erlang, 88
erlang:system_flag/2
    erlang, 88
erlang:trace/3
    erlang, 89

```

erlang:trace_info/2
 erlang, 91
erlang:trace_pattern/2
 erlang, 92
erlang:universaltime/0
 erlang, 93
erlang:universaltime_to_localtime/1
 erlang, 93
error_handler
 undefined_function/3, 95
 undefined_lambda/3, 95
error_logger
 add_report_handler/1, 100
 add_report_handler/2, 100
 delete_report_handler/1, 100
 error_msg/1, 99
 error_msg/2, 99
 error_report/1, 97
 error_report/2, 98
 format/2, 99
 info_msg/1, 99
 info_msg/2, 99
 info_report/1, 98
 info_report/2, 98
 logfile/1, 99
 start/0, 97
 start_link/0, 97
 swap_handler/1, 100
 tty/1, 99
error_msg/1
 error_logger, 99
error_msg/2
 error_logger, 99
error_report/1
 error_logger, 97
error_report/2
 error_logger, 98
eval/1
 file, 103
eval_everywhere/3
 rpc, 150
eval_everywhere/4
 rpc, 150
exists/1
 auth, 37
exit/1
 erlang, 71
 exit/2
 erlang, 71
 fault/1
 erlang, 71
 fault/2
 erlang, 71
file
 change_group/2, 102
 change_owner/2, 102
 change_owner/3, 102
 change_time/2, 102
 change_time/3, 102
 close/1, 102
 consult/1, 102
 del_dir/1, 103
 delete/1, 103
 eval/1, 103
 file_info/1, 103
 format_error/1, 104
 get_cwd/0, 104
 get_cwd/1, 104
 list_dir/1, 105
 make_dir/1, 105
 make_link/2, 105
 make_symlink/2, 105
 open/2, 106
 path_consult/2, 107
 path_eval/2, 107
 path_open/3, 107
 position/2, 107
 pread/3, 108
 pwrite/3, 108
 read/2, 108
 read_file/1, 108
 read_file_info/1, 109
 read_link/1, 110
 read_link_info/1, 110
 rename/2, 110
 set_cwd/1, 111
 sync/1, 111
 truncate/1, 111
 write/2, 111
 write_file/2, 111
 write_file_info/2, 112
 file_info/1
 file, 103
 find_executable/1
 os, 145

```

find_executable/2
  os , 145

float/1
  erlang , 72

float_to_list/1
  erlang , 72

format/2
  error_logger , 99

format_error/1
  disk_log , 52
  erl_ddll , 62
  file , 104
  inet , 131

gen_tcp
  accept/1, 116
  accept/2, 116
  close/1, 116
  connect/3, 116
  connect/4, 116
  controlling_process/2, 117
  listen/2, 117
  recv/2, 117
  recv/3, 117
  send/2, 118

gen_udp
  close/1, 119
  controlling_process/2, 119
  open/1, 119
  open/2, 119
  recv/2, 120
  recv/3, 120
  send/4, 120

get/0
  erlang , 73

get/1
  erlang , 73

get_all_env/0
  application , 29

get_all_env/1
  application , 29

get_all_key/0
  application , 29

get_all_key/1
  application , 29

get_application/0
  application , 30

get_application/1
  application , 30

get_args/0
  init , 139

get_argument/1
  init , 139

get_arguments/0
  init , 138

get_closest_pid/1
  pg2 , 147

get_cwd/0
  file , 104

get_cwd/1
  file , 104

get_env/1
  application , 30

get_env/2
  application , 30

get_file/1
  erl_prim_loader , 64

get_key/1
  application , 30

get_key/2
  application , 30

get_keys/1
  erlang , 73

get_local_members/1
  pg2 , 148

get_members/1
  pg2 , 147

get_object_code/1
  code , 44

get_path/0
  code , 40
  erl_prim_loader , 65

get_status/0
  init , 139

get_system_tracer/0
  seq_trace , 155

get_token/0
  seq_trace , 154

get_token/1
  seq_trace , 154

```

```

getaddr/2
  inet , 133
  sync/0, 127
  whereis_name/1, 127
  whereis_name/3, 127

getenv/1
  os , 145
  global_groups/0
    global_group , 126

gethostbyaddr/1
  inet , 131
  group_leader/0
    erlang , 73

gethostbyname/1
  inet , 131
  group_leader/2
    erlang , 73

gethostbyname/2
  inet , 132
  halt/0
    erlang , 73

gethostname/0
  inet , 132
  halt/1
    erlang , 74

getpid/0
  os , 146
  hd/1
    erlang , 74

global
  del_lock/1, 121
  del_lock/2, 121
  notify_all_name/3, 122
  random_exit_name/3, 122
  random_notify_name/3, 122
  re_register_name/2, 123
  re_register_name/3, 123
  register_name/2, 122
  register_name/3, 122
  registered_names/0, 122
  send/2, 123
  set_lock/1, 123
  set_lock/2, 123
  set_lock/3, 123
  start/0, 124
  start_link/0, 124
  stop/0, 124
  sync/0, 124
  trans/2, 124
  trans/3, 124
  trans/4, 124
  unregister_name/1, 124
  whereis_name/1, 124

global_group
  global_groups/0, 126
  info/0, 126
  monitor_nodes/1, 126
  own_nodes/0, 126
  registered_names/2, 126
  send/2, 127
  send/4, 127
  start/0, 128
  start_link/0, 128
  stop/0, 128
  sync/0, 127
  whereis_name/1, 127
  whereis_name/3, 127

  heart
    clear_cmd/0, 130
    set_cmd/1, 130
    start/0, 129

  host_file/0
    net_adm , 142

  inc_wrap_file/1
    disk_log , 52

  inet
    close/1, 132
    format_error/1, 131
    getaddr/2, 133
    gethostbyaddr/1, 131
    gethostbyname/1, 131
    gethostbyname/2, 132
    gethostname/0, 132
    peername/1, 132
    port/1, 132
    setopts/2, 133
    sockname/1, 132

  info/0
    global_group , 126

  info/1
    disk_log , 52

  info_msg/1
    error_logger , 99

  info_msg/2
    error_logger , 99

  info_report/1

```

```

error_logger , 98
info_report/2
    error_logger , 98
init
boot/1, 138
get_args/0, 139
get_argument/1, 139
get_arguments/0, 138
get_status/0, 139
reboot/0, 139
restart/0, 139
script_id/0, 140
stop/0, 139
integer_to_list/1
    erlang , 74
interpret/1
    code , 45
interpret_binary/3
    code , 45
interpreted/0
    code , 46
interpreted/1
    code , 46
is_alive/0
    erlang , 74
is_auth/1
    auth , 37
is_loaded/1
    code , 42
is_process_alive/1
    erlang , 74
join/2
    pg2 , 148
kernel_apply/3
    net_kernel , 144
leave/2
    pg2 , 148
length/1
    erlang , 74
lib_dir/0
    code , 43
lib_dir/1
    code , 43
link/1
    erlang , 75
list_dir/1
    file , 105
list_to_atom/1
    erlang , 75
list_to_binary/1
    erlang , 75
list_to_float/1
    erlang , 75
list_to_integer/1
    erlang , 75
list_to_pid/1
    erlang , 75
list_to_tuple/1
    erlang , 76
listen/2
    gen_tcp , 117
load/1
    application , 30
load/2
    application , 30
load_abs/1
    code , 41
load_binary/3
    code , 43
load_driver/2
    erl_ddll , 61
load_file/1
    code , 41
loaded_applications/0
    application , 31
loaded_drivers/0
    erl_ddll , 62
localhost/0
    net_adm , 142
log/2
    disk_log , 53
log_terms/2
    disk_log , 54
logfile/1
    error_logger , 99

```

```
make_dir/1                               monitor_nodes/1, 144
  file , 105
make_link/2                             node/0
  file , 105                           erlang , 78
make_ref/0                              node/1
  erlang , 77                           erlang , 78
make_symlink/2                         node_cookie/2
  file , 105                           auth , 38
                                         nodes/0
                                         erlang , 78
Module:config_change/3                  notify_all_name/3
  application , 33                     global , 122
Module:start/2                          now/0
  application , 34                     erlang , 78
Module:start_phase/3                   objfile_extension/0
  application , 34                     code , 44
                                         open/1
                                         auth , 37
                                         disk_log , 54
                                         gen_udp , 119
                                         wrap_log_reader , 163
                                         open/2
                                         file , 106
                                         gen_udp , 119
                                         wrap_log_reader , 163
                                         open_port/2
                                         erlang , 78
                                         os
                                         cmd/1, 145
                                         find_executable/1, 145
                                         find_executable/2, 145
                                         getenv/1, 145
                                         getpid/0, 146
                                         type/0, 146
                                         version/0, 146
                                         own_nodes/0
                                         global_group , 126
                                         parallel_eval/1
                                         rpc , 152
                                         path_consult/2
                                         file , 107
                                         path_eval/2
                                         file , 107
                                         path_open/3
                                         file , 107
```

```

peername/1
  inet , 132

permit/2
  application , 31

pg2
  create/1, 147
  delete/1, 147
  get_closest_pid/1, 147
  get_local_members/1, 148
  get_members/1, 147
  join/2, 148
  leave/2, 148
  start/0, 148
  start_link/0, 148
  which_groups/0, 148

pid_to_list/1
  erlang , 80

pinfo/1
  rpc , 152

pinfo/2
  rpc , 152

ping/1
  net_adm , 142

pmap/4
  rpc , 152

port/1
  inet , 132

position/2
  file , 107

pread/3
  file , 108

print/1
  seq_trace , 154

priv_dir/1
  code , 44

process_flag/2
  erlang , 81

process_flag/3
  erlang , 82

process_info/1
  erlang , 82

process_info/2
  erlang , 83

processes/0
  erlang , 83

purge/1
  code , 42

put/2
  erlang , 84

pwrite/3
  file , 108

random_exit_name/3
  global , 122

random_notify_name/3
  global , 122

re_register_name/2
  global , 123

re_register_name/3
  global , 123

read/2
  file , 108

read_file/1
  file , 108

read_file_info/1
  file , 109

read_link/1
  file , 110

read_link_info/1
  file , 110

reboot/0
  init , 139

recv/2
  gen_tcp , 117
  gen_udp , 120

recv/3
  gen_tcp , 117
  gen_udp , 120

register/2
  erlang , 84

register_name/2
  global , 122

register_name/3
  global , 122

registered/0
  erlang , 84

registered_names/0
  global , 122

registered_names/2

```

global_group, 126
rename/2
 file, 110
reopen/2
 disk_log, 57
reopen/3
 disk_log, 57
replace_path/2
 code, 41
reset_trace/0
 seq_trace, 155
restart/0
 init, 139
root_dir/0
 code, 43
round/1
 erlang, 85
rpc
 abcast/2, 150
 abcast/3, 150
 async_call/4, 152
 block_call/4, 149
 call/4, 149
 cast/4, 149
 eval_everywhere/3, 150
 eval_everywhere/4, 150
 multi_server_call/2, 151
 multi_server_call/3, 151
 multicall/3, 150
 multicall/4, 151
 nb_yield/1, 152
 parallel_eval/1, 152
 pinfo/1, 152
 pinfo/2, 152
 pmap/4, 152
 safe_multi_server_call/2, 151
 safe_multi_server_call/3, 151
 sbcast/2, 150
 sbcast/3, 150
 server_call/4, 150
 start/0, 149
 stop/0, 149
 yield/1, 152

safe_multi_server_call/2
 rpc, 151
safe_multi_server_call/3
 rpc, 151
 sbcast/2
 rpc, 150
 sbcast/3
 rpc, 150
 script_id/0
 init, 140
 self/0
 erlang, 85
 send/2
 gen_tcp, 118
 global, 123
 global_group, 127
 send/4
 gen_udp, 120
 global_group, 127
 seq_trace
 get_system_tracer/0, 155
 get_token/0, 154
 get_token/1, 154
 print/1, 154
 reset_trace/0, 155
 set_system_tracer/1, 155
 set_token/1, 154
 set_token/2, 153
 server_call/4
 rpc, 150
 set_cmd/1
 heart, 130
 set_cwd/1
 file, 111
 set_lock/1
 global, 123
 set_lock/2
 global, 123
 set_lock/3
 global, 123
 set_path/1
 code, 40
 erl_prim_loader, 65
 set_system_tracer/1
 seq_trace, 155
 set_token/1
 seq_trace, 154
 set_token/2
 seq_trace, 153

```

setelement/3
  erlang , 85

setopts/2
  inet , 133

size/1
  erlang , 85

sockname/1
  inet , 132

soft_purge/1
  code , 42

spawn/1
  erlang , 86

spawn/2
  erlang , 86

spawn/3
  erlang , 86

spawn/4
  erlang , 86

spawn_link/1
  erlang , 86

spawn_link/2
  erlang , 86

spawn_link/3
  erlang , 86

spawn_link/4
  erlang , 87

spawn_opt/4
  erlang , 87

split_binary/2
  erlang , 87

start/0
  auth , 37
  code , 39
  erl_ddll , 61
  error_logger , 97
  global , 124
  global_group , 128
  heart , 129
  pg2 , 148
  rpc , 149
  user , 161

start/1
  application , 32
  code , 39
  erl_boot_server , 59

start/2
  application , 32

start/3
  erl_prim_loader , 64

start_link/0
  code , 39
  erl_ddll , 61
  error_logger , 97
  global , 124
  global_group , 128
  pg2 , 148

start_link/1
  code , 39
  erl_boot_server , 59

start_type/0
  application , 32

statistics/1
  erlang , 88

stick_dir/1
  code , 44

stop/0
  auth , 37
  code , 43
  erl_ddll , 61
  global , 124
  global_group , 128
  init , 139
  rpc , 149

stop/1
  application , 32

swap_handler/1
  error_logger , 100

sync/0
  global , 124
  global_group , 127

sync/1
  disk_log , 57
  file , 111

takeover/2
  application , 33

term_to_binary/1
  erlang , 89

throw/1
  erlang , 89

time/0

```

erlang , 89
tl/1
 erlang , 89
trans/2
 global , 124
trans/3
 global , 124
trans/4
 global , 124
trunc/1
 erlang , 93
truncate/1
 disk_log , 58
 file , 111
truncate/2
 disk_log , 58
tty/1
 error_logger , 99
tuple_to_list/1
 erlang , 93
type/0
 os , 146

unblock/1
 disk_log , 58
undefined_function/3
 error_handler , 95
undefined_lambda/3
 error_handler , 95
unlink/1
 erlang , 93
unload_driver/1
 erl_ddll , 61
unregister/1
 erlang , 94
unregister_name/1
 global , 124
unstick_dir/1
 code , 45
user
 start/0, 161

version/0
 os , 146
whereis/1
 erlang , 94
whereis_name/1
 global , 124
 global_group , 127
whereis_name/3
 global_group , 127
which/1
 code , 45
which_applications/0
 application , 33
which_groups/0
 pg2 , 148
which_slaves/0
 erl_boot_server , 60
world/0
 net_adm , 142
world_list/2
 net_adm , 142
wrap_log_reader
 chunk/1, 162
 chunk/2, 162
 close/1, 163
 open/1, 163
 open/2, 163
write/2
 file , 111
write_file/2
 file , 111
write_file_info/2
 file , 112
yield/1
 rpc , 152